



FlexNet Publisher 2016 R2 SP1 (11.14.1.1)

License Administration Guide

Legal Information

Book Name: License Administration Guide
Part Number: FNP-111411-LAG00
Product Release Date: March 2017

Copyright Notice

Copyright © 2017 Flexera Software LLC. All Rights Reserved.

This product contains proprietary and confidential technology, information and creative works owned by Flexera Software LLC and its licensors, if any. Any use, copying, publication, distribution, display, modification, or transmission of such technology in whole or in part in any form or by any means without the prior express written permission of Flexera Software LLC is strictly prohibited. Except where expressly provided by Flexera Software LLC in writing, possession of this technology shall not be construed to confer any license or rights under any Flexera Software LLC intellectual property rights, whether by estoppel, implication, or otherwise.

All copies of the technology and related information, if allowed by Flexera Software LLC, must display this notice of copyright and ownership in full.

Intellectual Property

For a list of trademarks and patents that are owned by Flexera Software, see <http://www.flexerasoftware.com/intellectual-property>. All other brand and product names mentioned in Flexera Software products, product documentation, and marketing materials are the trademarks and registered trademarks of their respective owners.

Restricted Rights Legend

The Software is commercial computer software. If the user or licensee of the Software is an agency, department, or other entity of the United States Government, the use, duplication, reproduction, release, modification, disclosure, or transfer of the Software, or any related documentation of any kind, including technical data and manuals, is restricted by a license agreement or by the terms of this Agreement in accordance with Federal Acquisition Regulation 12.212 for civilian purposes and Defense Federal Acquisition Regulation Supplement 227.7202 for military purposes. The Software was developed fully at private expense. All other use is prohibited.

Contents

Introduction	11
1 Overview of Licensing	13
License Server	14
Using a License Server With License Files	15
2 Trusted Storage	17
Overview of Trusted Storage	17
Automated Delivery of Licenses to a License Server	17
Using Licenses From Trusted Storage on a License Server	18
Trusted Storage Components on a License Server	18
Using a License Server With Trusted Storage	19
Distribution of Node-Locked Licenses to Networked Machines	20
Activation Transaction Types	22
Comparison of Trusted Storage and License Files	22
License Files and Fulfillment Records	22
Locking of Licenses Using Hostid or Trusted Storage	24
Licensing in Virtual Environments	24
Binding in a Virtual Environment	24
Best Practices	25
3 Reading a License File	27
License File Format Overview	27
License File Syntax	28
SERVER Lines	28
VENDOR Lines	30
USE_SERVER Line	31
FEATURE and INCREMENT Lines	31

- Publisher-Defined Required Keywords 32
- Optional Publisher-Defined Keywords..... 33
- Optional Keywords Defined by the License Administrator..... 36
- Character Limitations in Keyword Values 37
- Sort Rules 37
- Changes in FEATURE and INCREMENT Line Format..... 37
- PACKAGE Lines..... 38
- UPGRADE Lines..... 40
- Order of Lines in the License File.....40**

- 4 Locating Licenses 43**
- Determining the Location of the License File.....43**
- Setting the License Search Path Using an Environment Variable.....44**
- Order of Searching for a License..... 45

- 5 Managing License Files 47**
- Modifying License Files.....47**
- Configuring the Port Used by the License Server..... 47

- 6 Hostids for Supported Platforms 49**
- Hostid Formats49**
- Obtaining System Hostids49**
- Special Hostids.....53**
- Ethernet Hostids54**
- Hostids to Support Virtualization Policy.....55**
- Hostids to Support Cloud Licensing55**

- 7 License Models 57**
- Floating (Concurrent) Licenses.....57**
- Node-Locked Licenses Using Hostid57**
- Mixed Node-Locked and Floating Licenses..... 58
- Counted vs. Uncounted Licenses58**
- Mobile Licensing59**
- Node-Locked to a Laptop Computer..... 59
- Node-locked to a FlexNet ID Dongle..... 60
- Node-Locked to a FlexNet ID Dongle with FLOAT_OK..... 60
- Using a FlexNet ID Dongle for Mobile Licensing Using a FLOAT_OK License 60
- FLEXID with FLOAT_OK Example..... 61
- License Borrowing with BORROW..... 61
- Initiating License Borrowing 62
- Application Interface..... 62
- Running the Imborrow Utility 62
- Setting the LM_BORROW Environment Variable Directly..... 62
- Borrowing a License..... 63

Clearing the Borrow Period	64
Checking Borrow Status	64
Returning a Borrowed License Early	64
Support for License Borrowing	64
Node-locked to a User Name	65
Fulfilled from a Prepaid License Pool	65
8 Selecting a License Server Machine	67
License Server Sockets	67
License Server CPU Time	67
License Server Disk Space	68
License Server Memory	68
Network Bandwidth for License Server	68
License Server Locally Mounted Disks	68
License Server Port	69
Running the License Server in a Cloud	69
9 License Server Manager “Imadmin”	71
Downloading and Installing Imadmin	72
System Requirements for Imadmin	72
Additional Installation Requirements	72
Using the License Server Installer	72
License Server Directory Structure	75
Upgrading Imadmin	77
Upgrading OpenSSL Libraries	78
Uninstalling Imadmin	79
Using Imadmin	80
Specifying the “conf” Folder	80
Manually Starting the License Server Manager	80
Manually Stopping the License Server Manager	81
Accessing the License Server Management Interface	82
Viewing the Imadmin Log Files	83
Managing Imadmin from the Command Line	83
Adding a Vendor Daemon to Imadmin	84
Configuring the License File Upload Directory	84
Configuring Imadmin License Server Manager as a Windows Service with a Three-Server Configuration	85
Accessing Imadmin License Server Manager as a Windows Service with a Three-Server Configuration	86
Installing Imadmin License Server Manager as an Operating System Service	88
Running FlexNet Publisher License Server as a System Service With Non-Elevated Privileges	90
Imadmin Command-line Arguments	92
Extending Imadmin License Server Capability	104
Using the Imadmin Web Service Interface	104
Creating an Imadmin Alerter Service	104

10 License Server Manager “Imgrd”	105
Imgrd Command-Line Syntax	105
Starting the License Server Manager on UNIX Platforms	107
Manual Start	107
Automatic Start	108
Starting the License Server Manager on Windows	109
Manual Start from the Command Line	109
Configuring the License Server Manager as a Windows Service	110
Configuring the License Server Manager Service for a Delayed Start	111
Manually Starting the License Server Using the Imtools Utility	112
Automatically Starting the License Server at System Startup	114
Three-Server Setup in Imtools	115
11 Migrating from Imgrd to Imadmin	117
A Fundamental Mode Change	117
Command Changes	118
Imadmin License Administration Functions	119
12 Using License Administration Tools	121
Command-Line Utilities	121
Common Arguments for Imutil	123
Imborrow	123
Initiating Borrowing	123
Clearing the Borrowed License Setting	124
Purging Expired Licenses	125
Determining Borrowed-License Status	125
Returning a Borrowed License Early	126
Imdiag	127
Imdown	127
Imhostid	128
Iminstall	132
Imnewlog	133
Impath	133
Imremove (in License File–Based Licensing)	134
Imremove (in Trusted Storage–Based Licensing)	136
Imreread	140
Imstat	140
Imswitch	142
Imswitchr	144
Imver	145
Imvminfo	145
Imtools (Windows only)	146
13 Managing the Options File	149

Creating an Options File	150
Options File Syntax	150
AUTOMATIC_REREAD	154
ACTIVATION_LOWWATER	154
ACTIVATION_EXPIRY_DAYS	154
BORROW_LOWWATER	155
DAEMON_SELECT_TIMEOUT	156
DEBUGLOG	156
EXCLUDE	156
EXCLUDE_BORROW	157
EXCLUDE_ENTITLEMENT	158
EXCLUDEALL	158
FQDN_MATCHING	159
GROUP	161
GROUPCASEINSENSITIVE	161
HOST_GROUP	162
INCLUDE	162
INCLUDE_BORROW	163
INCLUDE_ENTITLEMENT	164
INCLUDEALL	165
LINGER	166
MAX	166
MAX_BORROW_HOURS	168
MAX_OVERDRAFT	168
NOLOG	169
REPORTLOG	169
Reporting on Projects with LM_PROJECT	169
RESERVE	170
TIMEOUT	171
TIMEOUTALL	171
How the Vendor Daemon Uses the Options File	171
Rules of Precedence in Options Files	172
Options File Examples	172
Simple Options File Example	172
Limiting Access for Multiple Users	173
EXCLUDE Example	173
EXCLUDE_ENTITLEMENT Example	174
INCLUDE Example	174
INCLUDE_ENTITLEMENT Example	174
14 Ensuring License Availability	177
Redundancy Using the License Search Path	177
Limitations of Redundancy Using the License Search Path	178
Overview of Three-Server Redundancy	178
Configuring License Servers for Three-Server Redundancy	180

Managing License Servers in a Three-Server Redundant Configuration181

Using Other Capabilities with Three-Server Redundancy182

Troubleshooting Tips and Limitations for Three-Server Redundancy184

15 Managing Virtualized License Servers for File-Based Licensing 187

 Binding Solutions in a Virtual Environment. 187

Setting Up a Virtual License Server on Microsoft Hyper-V187

 Using the UUID Hostid 187

Setting Up a Virtual License Server on VMware ESXi or XenServer188

 Using the UUID Hostid 188

Additional Considerations189

Virtualization Support189

16 Licensing in a Cloud-Computing Environment 191

Licensing Challenges in a Cloud Environment191

Scope of Support for Cloud Licensing192

Use Cases for Licensing Software in the Cloud192

 Case 1: Traditional Served and Unserved Licensing in a Public Cloud 192

 Binding Elements Required for Case 1..... 193

 License Administrator Tasks for Case 1..... 193

 Case 2: Traditional Served and Unserved Licensing in a Virtual Private Cloud 194

 Binding Elements Required for Case 2..... 194

 License Administrator Tasks for Case 2..... 194

Hostids for Binding195

 Supported Hostid Types 195

 Retrieving and Specifying Hostids 196

17 IPv6 Support 199

Capabilities that Support IPv6199

Testing Considerations202

18 Managing Licenses from Multiple Software Publishers 203

Overview of Multiple License Management Strategies203

Multiple Systems204

 Starting the License Servers 204

 Using Imadmin..... 205

 Using Imgrd 206

One System with Multiple License Server Instances206

 Starting the License Servers 207

 Using Imadmin..... 207

 Using Imgrd 208

One System with One License Server and Multiple License Files209

 Starting the License Server 210

Using Imadmin	210
Using Imgrd	211
Managing Multiple License Files	211
Managing Multiple File in Imadmin	211
Managing Multiple Files in Imgrd	211
Defining the License File List	212
Additional Considerations	212
Combining License Files	212
Starting the License Server	213
Criteria for Combining License Files	213
How to Combine License Files	215
Version Component Compatibility	215
19 Troubleshooting	217
General Troubleshooting Hints	217
FLEXLM_DIAGNOSTICS	218
Level 1 Content	218
Level 2 Content	218
Level 3 Content (Version 6.0 or Later Only)	219
20 Error Codes	221
Error Message Format	221
Format 1 (short)	222
Format 2 (long)	222
Error Code Descriptions	222
21 Report Log File	233
Managing Report Log Output	233
Enabling Report Log Output for a Vendor Daemon	234
Redirecting Report Log Output for a Vendor Daemon	234
22 Debug Log File	235
Managing Debug Log Output	235
Capturing Debug Log Output for a License Server	235
Capturing Debug Log Output for a Particular Vendor Daemon	236
Redirecting Debug Log Output for a Running Vendor Daemon	236
Limiting Debug Log Output for a Vendor Daemon	236
License Server Diagnostics in the Debug Log	236
Debug Log Messages	237
Informational Messages	237
Configuration Problem Messages	239
Daemon Software Error Messages	240
23 Identifying FlexNet Publisher Versions	241

Version Compatibility Between Components241

Determining the License File Version242

24 Environment Variables 243

How to Set Environment Variables243

 Windows Registry 243

 Precedence 243

Environment Variables244

Index 249

Introduction

This document describes FlexNet Publisher licensing for license administrators. It describes how to setup and administer FlexNet Publisher licensing for license models that require a license server.:

Table 1 • *License Administration Guide* Chapter Overview

Section	Content
This section	An overview of the contents of this document.
Overview of Licensing	Overview of licensing and specifically licensing using license files.
Trusted Storage	An overview of licensing using license rights held in trusted storage.
Reading a License File	A description of the elements in a license file.
Locating Licenses	How to locate licenses so that they are available to FlexEnabled applications.
Managing License Files	Modifying license files.
Hostids for Supported Platforms	Details of hostids available by platform and information about choosing an Ethernet address as hostid.
License Models	Overview of basic license models and methods of licensing for laptops that may be provided by your software publisher.
Selecting a License Server Machine	What to consider when selecting the machine on which to install the license server software.
License Server Manager “ladmin”	Description of how to install and use ladmin as your license server.

Table 1 • *License Administration Guide* Chapter Overview

Section	Content
Migrating from Imgrd to Imadmin	A comparison of Imgrd and Imadmin.
License Server Manager “Imgrd”	How to use Imgrd as your license server.
Using License Administration Tools	How to use license administration tools to manage licenses and license servers.
Managing the Options File	Using the options file to control license utilization and the license server.
Ensuring License Availability	Methods of providing failover protection for license servers.
Managing Virtualized License Servers for File-Based Licensing	Virtualization of a license server.
Licensing in a Cloud-Computing Environment	Setup of licensing model in an Amazon EC2 environment.
IPv6 Support	Installing and configuring license servers in IPv6 and mixed IPv4 and IPv6 environments.
Managing Licenses from Multiple Software Publishers	Strategies for managing licenses from multiple software publishers.
Troubleshooting	Tips and information about generating additional diagnostic data.
Error Codes	A list of FlexNet Publisher error codes.
Report Log File	Enabling and managing report log output.
Debug Log File	Enabling and managing debug log output.
Environment Variables	Environmental variables that may be used with FlexNet Publisher.
Identifying FlexNet Publisher Versions	Version compatibility between components and brief details of functional changes for each major version of FlexNet Publisher.

1

Overview of Licensing

FlexNet Publisher is a method of providing software licensing that has two basic components:

- **FlexEnabled application** - the software application that requires a license.
- **A license** - contains the license rights that define how the software application can be used.

Typically the license defines:

- What software functionality can be used. Functions provided by the software can be separately licensed. The licensed functions are referred to as *features*. When multiple features are defined, different versions of the product can be licensed by including different feature sets. For example, the license for the 'demo' version of the product could include the feature 'trial', the 'standard' version of the product the features 'trial' and 'basic' and the 'professional' version 'trial', 'basic' and 'extend' features.
- What versions of the software can be used.
- How many copies of the software can be running.
- The systems on which the software can be used.
- The period during which the software can be used.

These and other items in the license define how the software can be used and collectively are referred to as a *license model*.

The license can be stored:

- **In a license file** - a text file, *file_name.lic*, whose contents are protected by signatures that are authenticated by the FlexNet Publisher licensing components.
- **In trusted storage** - a secure location whose contents are encrypted. Licenses are stored as *fulfillment records*. Fulfillment records in trusted storage can be read only by FlexNet Publisher licensing components.

The FlexEnabled application can obtain a license directly, either from a license file or from *local* trusted storage on the same machine. Some license models, described as *served*, provide licenses that are held centrally by a *license server* and used by FlexEnabled applications connected to the license server across a TCP/IP network.

This document describes how to install and use a license server to provide licenses for FlexEnabled products that use served license models. The basic license model that requires a license server is referred to by several names depending on the context:

- Concurrent
- Floating

Concurrent licenses allow a fixed number of concurrent users to use licensed features at any one time. The license server controls the use of these licenses, which are not normally locked to a specific machine, and *float* on the network. FlexNet Publisher provides for many variations of this basic license model, for example the use of a set of concurrent licenses can be restricted to a group of users.

License Server

The basic components of a FlexNet Publisher license server are as illustrated in the following diagram:

- **License server manager** - `lmadmin` (or `lmgrd`) supplied by your software supplier or available from Flexera Software.
- **License file** - Created by your software supplier. In this document the supplier of a FlexEnabled application is referred to as the *publisher*.
- **Vendor daemon** - Created by the publisher. Each publisher has their own vendor daemon. If you have FlexEnabled applications from several publishers, you will need to install multiple vendor daemons.
- **Debug log** - Written by the license server manager.




Figure 1-1: FlexNet Publisher license server

The following components may be present on a license server:

- **Options file** - optional file that you create. Use it to limit license usage; for example, to allocate particular licenses to a user or group of users.

- **Report log** - optional file that can be used by FlexNet Manager, Flexera Software's license management product. You enable report logging using the options file.
- **Trusted storage** - some publishers use trusted storage to store licenses. When trusted storage is used, the publisher provides additional components (not shown on [Figure 1-1](#)) that create trusted storage and add licenses to it. See [Trusted Storage](#) for an overview.

Using a License Server With License Files

The following gives an outline of the steps in installing a license server and using it to serve licenses from license files. For further information about each of these steps, read the relevant sections of this document.

1. Choose the machine(s) on which the license server(s) will be installed.
 - Determine the number of licenses and machines on which FlexEnabled applications will be installed. See [Selecting a License Server Machine](#) for further information.
 - Consider what method, if any, you want to use to ensure that, whenever possible, licenses are available to your end users. See [Ensuring License Availability](#) for further information.

2. Install the license server components.

The publisher will supply a copy of their vendor daemon and instructions for installing it. Additionally, either the publisher provides the license server manager (`lmadmin` or `lmgrd`), or you can download a copy from the Flexera Software website. It is recommended that you install the latest version of the license server manager.

3. Obtain details of the license server machine(s) and send them to the publisher.

Normally publishers supply concurrent licenses that are locked to a specific license server. When licenses are held in license files, they are locked to the license server using an identity obtained from the machine. This identity is called a *hostid* and is platform-specific. There are several different hostids available for each platform. The publisher will provide instructions on what hostid they are using for your licenses and platforms. They may supply an application that you can run to obtain the hostid or ask you to use the FlexNet Publisher utility, `lmhostid`, which you can download from the Flexera Software website. If you are using `lmadmin`, it displays the standard hostids for the machine on which it is running in **System Information**.

Depending on the license model, the publisher may require other details of your license server, the machine on which it is running, and details of your network.

4. Install licenses on the license server.

The publisher may specify a particular location for the license files on the license server. When no specific location is required, see information in [Locating Licenses](#) for instructions.

5. Install the FlexEnabled application on end user machines.

The publisher will supply installation instructions for installing the FlexEnabled application.

6. Set up end user machines to access the license server.

There are several methods of configuring the end user machine to access a single license server or multiple license servers. These depend on the contents of the license files supplied by the publisher and your license server(s) configuration. See information in [Locating Licenses](#) for instructions.

7. Optionally, create an options file.

If you want to limit license usage, configure logging, or turn off the automatic reread of licenses, create an options file and install it in the same directory as the vendor daemon. See instructions in [Managing the Options File](#).

8. Configure and start up the license server manager.

There is a fundamental difference between the configuration of `lmadmin` and `lmgrd`, so the processes required for each are separately outlined here:

lmadmin - The configuration settings are permanent and mainly set using the user interface. For details see `lmadmin` Online help and [Using lmadmin](#).

lmgrd - the configuration settings are set when `lmgrd` is started. They are not persistent. For details see [License Server Manager "lmgrd"](#).

You can manage and monitor the operation of the license server using the license server manager. `lmadmin` provides direct management and monitoring of the license server through its user interface; `lmgrd` provides limited information as command-line output. Additional utilities are provided on the Flexera Software website for management and monitoring of the license server. For details, see [Using License Administration Tools](#). For more comprehensive monitoring and reporting of license usage, use FlexNet Manager. FlexNet Manager is a Web-based administration and reporting tool for FlexNet licenses and license servers.

2

Trusted Storage

Some publishers use trusted storage to store licenses. They might store all of their licenses in trusted storage or use a combination of licenses held in license files and in trusted storage. You can use a single license server to serve licenses from both license files and trusted storage.

Overview of Trusted Storage

Trusted storage is a secure location that is locked to the machine on which it is located using a combination of machine identities. The contents of trusted storage are encrypted and can only be accessed by FlexEnabled components. This method of storing licenses enables your publisher to provide additional license models and automate some licensing processes.

Automated Delivery of Licenses to a License Server

Trusted storage is maintained by licensing life-cycle operations, such as license activations, returns, repairs, and upgrades. These life-cycle operations are performed through transactions normally issued over a network connection between the license server and the publisher's activation server. However, when a network connection is not available, the messages that implement these transactions can be transmitted by other means.

Activation is the basic licensing life-cycle operation between the license server and the publisher's activation server. This operation configures your trusted storage for specific use by the publisher and writes a *fulfillment record* to it. The fulfillment record contains licenses defined using a similar format to that used for licenses held in license files.

The remaining life-cycle operations between a license server and the publisher's activation server maintain the trusted-storage licenses and are optional:

- **Return** - Returns a fulfillment record (and the licenses it contains) from trusted storage to the publisher server it was issued by.
- **Repair** - Repairs compromised fulfillment records in trusted storage.
- **Upgrade to a new version** - The old license is returned to the publisher's activation server so that entitlement to the upgrade can be checked and new licenses transmitted using an activation operation.

- **Rehost of license server** - When you need to move a license server to a different machine, a combination of return and then activation operations can provide a completely automated transfer.



Note • *Not all publishers provide these facilities.*

Using Licenses From Trusted Storage on a License Server

Two types of licenses can be used in trusted storage on a license server. Your publisher may provide either or both of these types of license. They are used to provide different licensing models.

- **Concurrent** - allows a fixed number of concurrent users to use licensed features at any one time. The license server controls the use of these licenses, which are not normally locked to a specific machine, and *float* on the network. FlexNet Publisher provides for many variations of this basic license model, for example the use of a set of concurrent licenses can be restricted to a group of users.
- **Activatable** - licenses are distributed by the license server to network machines to provide local licenses for FlexEnabled applications. In this license model FlexEnabled components on the network machine request a license from the license server. License rights held in trusted storage on the license server are transferred to trusted storage on the network machine. This provides a license that is locked to the network machine. Depending on which license models your publisher is providing, these licenses may be of limited duration and automatically return to the license server when they expire on the network machine, or may be transferred to the network machine 'permanently'.

Trusted Storage Components on a License Server

The basic components of a FlexNet Publisher license server that uses licenses held in trusted storage are as illustrated in the following diagram:

- **License server manager** - lmadm (or lmgd) supplied by your publisher or available from Flexera Software.
- **Bootstrap license file** - Created by your publisher. Required for starting the license server manager when the license server is using trusted storage to store all its licenses.
- **Vendor daemon** - Created by the publisher. This must be the publisher vendor daemon that can access trusted storage. Ensure that you always use the correct vendor daemon supplied by the publisher: an earlier version that is only able to use license files will not be able to use licenses held in trusted storage.
- **Trusted storage** - Contains licenses in fulfillment records.

- **Server activation utility** - A FlexEnabled component that manages the transactions with the publisher server and creates and manages the contents of trusted storage.




Figure 2-1: License Server Using Licenses in Trusted Storage

The following components not shown on the diagram may be present on the license server:

- **Debug log** - Written by the license server manager.
- **Options file** - Optional file that you create.
- **Report log** - Optional file used by FlexNet Manager.

Using a License Server With Trusted Storage

The following gives an outline of the steps in installing a license server and using it to serve licenses from trusted storage. For further information about each of these steps read the relevant sections of this document.

1. Choose the machine(s) on which the license server(s) will be installed.
 - Determine the number of licenses and machines on which FlexEnabled applications will be installed. See [Selecting a License Server Machine](#) for further information.
 - Consider what method, if any, you want to use to ensure that whenever possible licenses are available to your end users. See [Ensuring License Availability](#) for further information.

2. Install the license server components.

The publisher will supply a copy of his vendor daemon and instructions for installing it. The latest license server manager, `lmadmin`, displays details of licenses held in trusted storage; `lmgrd` includes information about concurrent licenses held in trusted storage but does not display details of activatable licenses. Therefore, it is recommended that you install `lmadmin` as your license server manager. Either the publisher provides this component, or you can download a copy from the Flexera Software website. It is recommended that you install the latest version of the license server manager.

3. Install licenses on the license server.

The publisher will supply instructions and software that requests licenses from the publisher server. This process may be completely transparent to you. The publisher provides the interface for the installation of licenses so publisher's licensing solutions may differ greatly. FlexNet Publisher is designed to allow publishers maximum flexibility in licensing models and processes.

4. Install the FlexEnabled application on end user machines.

The publisher will supply installation instructions for installing the FlexEnabled application and optionally any further FlexEnabled components.

5. Set up end user machines to access the license server to obtain concurrent licenses.

There are several methods of configuring the end-user machine to access a single license server or multiple license servers. These depend on the contents of any license files that may optionally be supplied by the publisher and your license server(s) configuration. See information in [Locating Licenses](#) for instructions.

6. Optionally, create an options file.

If you want to limit license usage, configure logging or turn off the automatic reread of licenses, create an options file and install it in the same directory as the vendor daemon. See instructions in [Managing the Options File](#).

7. Configure and start up the license server manager.

8. Optionally, install node-locked licenses on end user machines using activatable licenses from the license server.

The publisher will supply instructions for requesting licenses from the license server. Additional components may be installed on the end user machine for this licensing model, see [Distribution of Node-Locked Licenses to Networked Machines](#).

Distribution of Node-Locked Licenses to Networked Machines

The distribution of licenses from a license server to machines running FlexEnabled applications via a network is one license model that can be provided using activatable licenses held in trusted storage on a license server. FlexEnabled components on the network machine send a request for a license to the license server. The vendor daemon processes this request and if a suitable license is available transfers it to the network machine.

The FlexEnabled components on the network machine install the license in trusted storage. Trusted storage is locked to the network machine and thus licenses held in trusted storage are node-locked to that machine.




Figure 2-2: FlexEnabled components for trusted storage on a network machine

The FlexEnabled components required to implement the distribution of node-locked licenses to networked machines using trusted storage are:

- **License server manager** - Use `lmadmin` as the license server manager as it displays details of activatable licenses held in trusted storage.
- **Vendor daemon** - Created by the publisher. This must be the publisher vendor daemon that can access trusted storage. Ensure that you always use the correct vendor daemon supplied by the publisher: an earlier version that is only able to use license files will not be able to use licenses held in trusted storage.
- **Trusted storage on license server** - Contains activatable licenses that can be transferred to a networked machine. Concurrent licenses can only be used to implement floating license models.
- **Server activation utility** (not shown) - The FlexEnabled component on the license server that requests and loads licenses into the server's trusted storage from the publisher. This utility also manages the contents of the server's trusted storage through return, repair, and modify requests.
- **Application activation utility** - A FlexEnabled component that requests a license from the enterprise license server or the publisher's activation server and creates and manages the contents of trusted storage. The publisher can integrate this functionality into a component that provides other functions (for example, the utility could be integrated into the FlexEnabled application installer).
- **Trusted storage on the network machine** - Contains licenses locked to the machine.
- **FlexEnabled application** - The application that requires the license. Note that this component must have been built by your publisher so that it can access trusted storage. You must ensure that you use the correct version of the application.

You can use the `options` file to restrict the distribution of node-locked licenses to network machines. See [Managing the Options File](#) for details.

Activation Transaction Types

FlexNet Publisher supports two transaction types:

- **Composite Transactions**—From FlexNet Publisher 11.14.0, composite transactions are fully supported for all servers. From this version onwards, it is best practice to use composite transactions for all interactions with servers.
- **Single-Action Transactions**—Single-action transactions perform one activation action per transaction. For example, using single-action transactions to activate two fulfillment records from a license server to a FlexEnabled client involves issuing two separate transactions.

From FlexNet Publisher version 11.14.0, single-action transactions have been deprecated.

Composite Transactions

Composite transactions are supported for life-cycle operations between the publisher's activation server and the license server, as well as between the license server and FlexEnabled clients. A single composite transaction between the publisher's activation server and the license server uses one request from the license server and one response from the publisher's activation server to perform any number of activations, repairs, returns, and upgrades on the license. For example, a composite transaction can perform any of the following licensing life-cycle operations, providing greater flexibility in managing trusted-storage license rights:

- Return one or more fulfillment records
- Activate one or more fulfillment records
- Modify one or more fulfillment records (for example, to change the license count)
- Combinations of these actions to perform partial or full returns or upgrades

Additionally, composite transactions store more details about the activation than single-action transactions do, allowing a better chance to fully recover a trusted storage on the license server should errors occur.

Comparison of Trusted Storage and License Files

This section gives an overview of the significant differences between FlexEnabled products that use trusted storage and those that use license files. However, significant these changes might be, the methods for defining license rights in trusted storage are based on the methods for defining rights in license files. So if you have been using FlexEnabled products for years, the majority of your knowledge is directly applicable to licenses held in trusted storage.

License Files and Fulfillment Records

The license model is defined primarily in the feature definition lines (FEATURE and INCREMENT) in a license file. There are the same feature definition lines inside fulfillment records in trusted storage. See the following diagram that shows a typical `lmadmin` display for a fulfillment record.

Figure 2-3: License server fulfillment record displayed by Imadmin

The fulfillment record PR-589df128 provides 10 activatable licenses for the product PRprofessional. Each activatable license licenses two features: PRbasic and PRadvanced. These two feature definition lines (in this example INCREMENT lines) are packaged together in a single fulfillment record.

Licenses held in trusted storage use all the mandatory fields and may contain most of the attributes described in [Reading a License File](#). The following are the exceptions:

- **BORROW** - Normally this feature definition line attribute is not used for licenses held in trusted storage, the publisher will provide this licensing model using the [Distribution of Node-Locked Licenses to Networked Machines](#) using trusted storage on the network machine.
- **HOSTID** - Normally this feature definition line attribute is not required for licenses held in trusted storage, see [Locking of Licenses Using Hostid or Trusted Storage](#) for details of how licenses are locked to a host machine.
- **SUPERSEDE** - This feature definition line attribute is not supported for licenses held in trusted storage. A combination of return and activation operations are used to remove the license for the old version of the application and replace it with a new license.

The following line types are not supported in trusted storage:

- UPGRADE (a combination of returns and activations are used for an upgrade)
- PACKAGE (a fulfillment record effectively packages multiple feature definition lines)



Note • When other functions for package suites are required, a license file with a PACKAGE line can be provided.

- SERVER (not needed)
- VENDOR (lmadm provides direct vendor-daemon configuration)
- VM_PLATFORMS (not needed, deprecated)
- USE_SERVER (not needed)

Locking of Licenses Using Hostid or Trusted Storage

When license files are used, licenses are locked to a machine using a hostid. This identifies either the machine or a FlexNet ID dongle that is attached to a machine. The hostid is incorporated into the licenses supplied by the publisher so you must supply details of hostids before the publisher can provide your licenses. This procedure is repeated when licenses need to be moved to another machine.

Trusted storage is locked to the machine on which it is created using machine identities retrieved automatically by the FlexEnabled components when trusted storage is created. The licenses held in trusted storage are locked to the machine because they are held securely within trusted storage.

Licensing in Virtual Environments

The server-side activation utility can run inside a virtual machine. See [Chapter 15, "Virtualization Support,"](#) for the list of hypervisors that FlexNet Publisher supports.

Binding in a Virtual Environment

FlexNet Publisher automatically uses the appropriate binding elements when running in a virtual environment, if they are available. Binding is to differentiate between physical and virtual environments and the legacy bind-to-VMID policy is deprecated. The binding elements are:

- **MAC address** - used on physical environments is now used in virtual environments as well and is a deal breaker.
- **UUID** (universally unique ID) - A binding identity used to configure trusted storage on the virtual machine, previously the only binding identity used in virtual environments; this is now a deal breaker.
- **Generation ID**—A property of a virtual machine available in some environments. Where it is available it is used as a binding identity; it is a deal breaker.

A binding item is a deal breaker if, when it changes, trust should be lost regardless of the number of binding items that still match. Since all binding identities used in virtual environments are deal breakers, trust will always be lost if any of them change.

Best Practices

To Avoid Trusted-Storage Breakage

If the publisher chooses to bind trusted storage to the VMID, this binding breaks should the UUID (from which the VMID is derived) ever change or is no longer available. The break prevents license leakage when virtual machine images are cloned. However, if you manage a virtualized environment where virtual machines are moved between different native (physical) systems, you do not want trusted storage to break each time you move a machine instance.

To prevent breakage, use these best practices:

- Do not change the MAC address of the virtual machine.
- Do not change the UUID of the virtual machine when it is moved. (Normally, UUIDs change only if the virtual machine is cloned.)
- Save the configuration file (or at least the UUID) of each virtual machine on which trusted-storage license activation is performed. This file ensures that the UUID value used at the time of activation is available should you need to revert to this value.
- Should trusted storage break, use the activation utility to issue a repair request; or reset the virtual machine's UUID to the value it had at activation time (powering the machine off and then on after the reset).

To Avoid Issues with the Licensing Life-Cycle Operations

Although both composite and single-action transactions are supported for licensing life-cycle operations between the publisher's activation server and the license server, best practice is always to use composite transactions. Issues can arise if you attempt to mix composite and single-action transactions, mainly because composite transactions support UMN3 and UMN5 while single-action transactions do not. For example, if a composite transaction is used initially to activate licenses on a virtual machine, the UMN3, if obtained, becomes the primary UMN for requester verification. If a single-action transaction is used later to return a license, the process fails because the return request contains no UMN3 to identify the requesting machine.

3

Reading a License File

A license file contains information required to manage licenses for a FlexEnabled application. This information includes:

- License server names and hostids
- VENDOR names and paths to vendor daemon executables
- Feature information

The license file must be accessible to systems that run the FlexEnabled application or a license server. For details see [Locating Licenses](#) and [Ensuring License Availability](#).

License File Format Overview

License files begins with either a single SERVER line or three SERVER lines (when configured for three-server redundancy) followed by one or more VENDOR lines, followed by one or more FEATURE or INCREMENT lines. In some cases, the license file requires no SERVER line and no VENDOR line.



Note • *Eight-bit Latin-based characters are fully supported in license files, options files, log files, and FlexEnabled application environments.*

See [Counted vs. Uncounted Licenses](#) for more information on SERVER and VENDOR line requirements.

You can modify these elements in the license file:

- On the SERVER line:
 - Host names on the SERVER lines
 - TCP/IP port numbers
 - HEARTBEAT_INTERVAL and PRIMARY_IS_MASTER properties
- On the VENDOR line:

- Paths to the vendor daemon.
- Options file paths
- TCP/IP port numbers (for firewall support only)
- The USE_SERVER line.
- On the feature definition lines:
 - The values in *keyword=value* pairs on FEATURE lines, if *keyword* is specified in lowercase
 - You can use the \ line-continuation character to break up long lines.

See Also[Ensuring License Availability](#)[Counted vs. Uncounted Licenses](#)

License File Syntax

This section describes the contents of the license file, including SERVER lines and VENDOR lines. This is an example of a license file for a single VENDOR name with two features.

```
SERVER my_server 17007ea8 1700
VENDOR sampled
FEATURE f1 sampled 1.000 31-dec-2020 10 SIGN="<...>"
FEATURE f2 sampled 1.000 31-dec-2020 10 SIGN="<...>"
```

This example allows the license server, called **my_server** with the hostid **17007ea8**, to serve ten floating licenses for each feature, **f1** and **f2** to any user on the network.

SERVER Lines

The SERVER line specifies the host name and hostid of the license server and the TCP/IP port number of the license server manager (lmadmin or lmgrd). Normally a license file has one SERVER line. Three SERVER lines mean that you are using license servers configured for three-server redundancy. The absence of a SERVER line means that every feature definition line in the license file is uncounted.

The hostids from the SERVER lines are computed into the license key or signature on every feature definition line. For this reason, make sure you keep SERVER lines together with any feature definition lines as they were sent from the software publisher.

The format of the SERVER line is:

```
SERVER host hostid [port] [PRIMARY_IS_MASTER] [HEARTBEAT_INTERVAL=seconds]
```

For example:

```
SERVER my_server 17007ea8 21987
```

The following table describes the attributes on this line.

Table 3-1 • SERVER Line Format

Field	Description
<i>host</i>	The system host name or IP address. String returned by the UNIX hostname or uname -n command. On Windows 2000/XP, ipconfig /all returns the host name.
<i>hostid</i>	Usually the string returned by the lmhostid command. This is changed only by your publisher.
<i>port</i>	<p>TCP/IP port number to use. A valid number is any unused port number in the range 0 to 65535. On UNIX, choose a port >1024, since those <1024 are privileged port numbers. If no TCP/IP port number is specified, one of the default ports in the range 27000 to 27009 is used.</p> <p>You must specify a port number when the SERVER line defines license servers configured for three-server redundancy.</p> <p> Note • Those producers concerned about potential DoS attacks based on knowledge of common license server ports may want to consider specifying a server port outside the range 27000 to 27009.</p>
PRIMARY_IS_MASTER	<p>Used with license servers configured for three-server redundancy to indicate how master control is transferred between the primary and secondary servers.</p> <ul style="list-style-type: none"> • If this is set and the primary server goes down, when the primary server comes back up again, it will always become the master. • If this is not set and the primary server goes down, the secondary server becomes the master and remains the master even when the primary server comes back up. The primary can only become the master again when the secondary license server fails. <p>If both primary and secondary go down, licenses are no longer served. The tertiary server never becomes the master.</p> <p>This parameter is optional and is placed on the first SERVER line in the license file. You must be running a version 10.8 or later vendor daemon to use this parameter.</p>

Table 3-1 • SERVER Line Format

Field	Description
HEARTBEAT_INTERVAL= <i>seconds</i>	<p>Used with license servers configured for three-server redundancy to indicate how long a license server waits to receive a heartbeat from another license server in the triad before shutting itself down. The <i>seconds</i> value is used in the following equation to calculate the timeout:</p> <ul style="list-style-type: none"> • $\text{timeout} = (3 \times \text{seconds}) + (\text{seconds} - 1)$ <p>Valid timeout value is 0-120. If not specified, the default value for <i>seconds</i> is 20, equating to an actual timeout value of 79 seconds. Valid values for the <i>seconds</i> value are 0–30.</p> <p> Note • When the <i>seconds</i> value exceeds 30, <i>lmadmin</i> displays the Heartbeat Interval value as -1 along with the an error message "Invalid three server redundancy configuration, valid timeout values are 0 - 120".</p> <p>This parameter is optional and is placed on the first SERVER line in the license file. You must be running a version 10.8 or later vendor daemon to use this parameter.</p>

See Also[Ensuring License Availability](#)

VENDOR Lines

The VENDOR line specifies the daemon name and path. The license server uses this line to start the vendor daemon, and the vendor daemon reads it to find its options file. The format of the VENDOR line is shown below.

```
VENDOR vendor [vendor_daemon_path]\  
                [[OPTIONS=]options_file_path] [[PORT=]port]
```

where:

Table 3-2 • VENDOR Line Format

Field	Description
<i>vendor</i>	Name of the vendor daemon used to serve some features in the file. This name cannot be changed.

Table 3-2 • VENDOR Line Format

Field	Description
<i>vendor_daemon_path</i>	<p>Optional path to the executable for this daemon. Generally, the license administrator is free to install the vendor daemon in any directory. It is recommended, however, that it be installed in a local directory on the license server.</p> <p>If omitted, the license server looks for the vendor daemon binary in:</p> <ul style="list-style-type: none"> • the current directory • the path specified in license server's \$PATH environment variable • in the directory where the license server is located <p>If <i>vendor_daemon_path</i> is blank, then any option or TCP/IP port number specifications require the <code>OPTIONS=</code> and <code>PORT=</code> strings.</p>
<i>options_file_path</i>	<p>Full path to the options file for this daemon. An options file is not required.</p> <p>If omitted, the vendor daemon, by default, looks for a file called vendor.opt (where <i>vendor</i> is the vendor daemon name) located in the same directory as the license file.</p>
<i>port</i>	<p>Vendor daemon TCP/IP port number.</p> <p>A valid number is any unused port number in the range 0 to 65535. On UNIX, choose a port >1024, since those <1024 are privileged port numbers.</p> <p>The default, if <i>port</i> is not specified, is chosen by the operating system at run-time. Sites with Internet firewalls need to specify the TCP/IP port number the daemon uses. If a TCP/IP port number is specified on the VENDOR line, there may be a delay restarting the vendor daemon.</p>

See Also

[Managing the Options File](#) for further information regarding options file contents.

USE_SERVER Line

The `USE_SERVER` line takes no arguments and has no impact on the license server. When the application sees the `USE_SERVER` line, it ignores everything in the license file except the preceding `SERVER` lines and transfers checkout validation to the vendor daemon.

`USE_SERVER` is recommended since it improves performance when a license server is used. For uncounted features, `USE_SERVER` is used to force logging of usage by the daemons.

FEATURE and INCREMENT Lines

A `FEATURE` and `INCREMENT` lines describe the license model for a product. Only the first `FEATURE` line for a given feature name is processed by the vendor daemon. If you want to have additional copies of the same feature (for example, to have multiple node-locked, counted features), then you must use multiple `INCREMENT` lines. `INCREMENT` lines form license groups, or *pools*, based on the following fields:

- feature name

- version
- DUP_GROUP
- FLOAT_OK
- HOST_BASED
- HOSTID
- PLATFORM
- USER_BASED
- VENDOR_STRING (if configured by the publisher as a pooling component)
- TZ
- VM_PLATFORMS (deprecated)

If two lines differ by any of these fields, a new group of licenses, called a *license pool*, is created in the vendor daemon, and this group is counted independently from other license pools with the same feature name. A FEATURE line does not give an additional number of licenses, whereas an INCREMENT line always gives an additional number of licenses.

The basic feature definition line format is:

```
{FEATURE|INCREMENT} feature vendor feat_version exp_date num_lic [optional_attributes] SIGN="<...>"
```

Publisher-Defined Required Keywords

The six fields after the feature definition line keyword are required and have a fixed order. They are defined by the software publisher and cannot be changed. [Table 3-3](#) presents these fields in the order they must appear.

Table 3-3 • Feature Definition Line Required Fields

Field	Description
<i>feature</i>	Name given to the feature by the software publisher.
<i>vendor</i>	Name of the vendor daemon; also found in the VENDOR line. The specified daemon serves this feature.
<i>feat_version</i>	Version of this feature that is supported by this license. When this field contains a date with the format <i>yyyy.mmdd</i> , this defines a date-based version that you can set as an Alert in the license server manager, <code>lmadmin</code> . In this case, <i>mmdd</i> must be in the range 101 to 1231 and valid (for example, <i>2020.1131</i> is not a valid date). For <i>dd</i> , both digits must be specified (for example, <i>2020.111</i> means January 11, 2020).

Table 3-3 • Feature Definition Line Required Fields

Field	Description
<code>exp_date</code>	Expiration date of license in the format <code>dd-mm-yyyy</code> , for example, 31-dec-2020.  Note • If <code>exp_date</code> is the string "permanent" or the year is 0 (or 00, 000, 0000) then the license never expires.
<code>num_Lic</code>	Number of concurrent licenses for this feature. If the <code>num_Lic</code> is set to the string "uncounted" or 0, the licenses for this feature are uncounted and no license server is required but a <code>hostid</code> on the FEATURE line is required. See Counted vs. Uncounted Licenses .
SIGN= <i>sign</i> or AUTH= ...	SIGN= signature to authenticate this FEATURE line. If your publisher has deployed his vendor daemon using the common vendor daemon technology, signatures are embedded within the AUTH= keyword. Contact your publisher for further details.  Note • Common Vendor Daemon is now deprecated.

Optional Publisher-Defined Keywords

Table 3-4 lists attributes that may appear in a FEATURE or INCREMENT line. They are supplied at the discretion of the software publisher to define the license model. If present in the FEATURE or INCREMENT line, they must remain there and cannot be altered by the end user. These attributes have a `keyword=value` syntax where `keyword` is in uppercase.

Table 3-4 • Attributes Set by the Software Publisher

Attribute	Description
BORROW [=n]	Enables license borrowing for a particular feature definition line. <code>n</code> is the number of hours that the license is borrowed. The default borrow period is 168 hours, or one week.

Table 3-4 • Attributes Set by the Software Publisher

Attribute	Description
DUP_GROUP=...	<p>The syntax is:</p> <p>DUP_GROUP=NONE[SITE][UHDV]</p> <p>U = DUP_USER</p> <p>H = DUP_HOST</p> <p>D = DUP_DISPLAY</p> <p>V = DUP_VENDOR_DEF</p> <p>Any combination of UHDV is allowed, and the DUP_MASK is the OR of the combination. For example, DUP_GROUP=UHD means the duplicate grouping is (DUP_USER DUP_HOST DUP_DISPLAY), so for a user on the same host and display, additional uses of a feature do not consume additional licenses.</p>
FLOAT_OK [=server_hostid]	<p>Enables mobile licensing via FLEXID with FLOAT_OK for a particular feature definition line. This feature definition line must also be node-locked to a FLEXID.</p> <p>When FLOAT_OK=server_hostid is specified on a FEATURE line:</p> <p>The server_hostid must refer to the same host that appears on the SERVER line of the license file.</p> <p>The license server runs only on the system with the hostid that lmhostid returns equal to the server_hostid specified with FLOAT_OK.</p>
HOSTID= "hostid1 [hostid2 ... hostidn]"	<p>Id of the host to which the feature line is bound. <i>hostid</i> is determined with the <code>lmhostid</code> utility. This field is required for uncounted licenses; but can be used for counted licenses as well. See Hostids for Supported Platforms for more information.</p> <p></p> <p>Note • <i>Host names generated dynamically will change the composite hostid value.</i></p>
HOST_BASED[=n]	Host names must be specified in INCLUDE statements in the options file, and the number of hosts is limited to <i>num_Lic</i> , or the number specified in <i>=n</i> .
ISSUED=dd-mmm-yyyy	Date issued.
ISSUER="..."	Issuer of the license.
NOTICE="..."	A field for intellectual property notices.

Table 3-4 • Attributes Set by the Software Publisher

Attribute	Description
ONE_TS_OK	<p>Detects when a node-locked uncounted license is used by an application running under remote desktop.</p> <p>The following are the two scenarios where you can expect 178 and 179 error codes:</p> <ul style="list-style-type: none"> • -178: Internal error, please report to Flexera Software LLC. This error occurs when an administrator, performs more than one remote desktop checkout on more than one terminal server remote client. • -179: Only one terminal server remote client checkout is allowed for this feature. This error occurs when a normal user, performs more than one remote desktop checkout on more than one terminal server remote client. <p> Note • <i>ONE_TS_OK</i> attribute is only used with uncounted licenses and is not supported with counted (served) licenses.</p>
OVERDRAFT=<i>n</i>	The overdraft policy allows a software publisher to specify a number of additional licenses which users are allowed to use, in addition to the licenses they have purchased. This allows your users to not be denied service when in a “temporary overdraft” state. Usage above the license limit is reported by the FlexNet Manager reporting tool.
SN=<i>serial_num</i>	Serial number, used to identify FEATURE or INCREMENT lines.
START=<i>dd-mmm-yyyy</i>	Start date.
SUITE_DUP_GROUP=...	Similar to DUP_GROUP, but affects only the enabling FEATURE line for a package suite. It limits the total number of users of the package to the number of licenses, and allows the package to be shared among the users that have the SUITE checked out.
SUPERSEDE= <i>"f1 f2 ..."</i>	If this appears, all INCREMENT or FEATURE lines for the specified feature that were issued earlier than the ISSUED date for the SUPERSEDE are <i>superseded</i> by this line and become ineffective. (SUPERSEDE also overrides those INCREMENT and FEATURE lines for the feature that have no ISSUED date.)
SUPERSEDE_SIGN= {f1:xxxx, f2:xxxx}	Overrides the license models of all feature definition lines or package lines defined as the value.
SUPERSEDE_SIGN= {p1:xxxx, p2:xxxx}	

Table 3-4 • Attributes Set by the Software Publisher

Attribute	Description
TS_OK	FlexNet Publisher detects when a node-locked uncounted license is running under Windows Terminal Server. To run the application via a Terminal Server client window, TS_OK must be added to the FEATURE line. Without TS_OK, a user running on a Terminal Server client is denied a license.
	
	Note • TS_OK attribute is only used with uncounted licenses and has no effect on counted (served) licenses.
TZ= [SERVERTZ] <[+-]hh<.30 .45> <:[+-]hh<.30 .45>>>	Enforces license usage for a feature relative to a time zone; where the time zone is specified and measured relative to Greenwich Mean Time (GMT). The computer system on which the FlexEnabled application is running must be within the specified time zone or range of time zones, or in the same time zone as the license server (using the value SERVERTZ).
USER_BASED[=n]	Users must be specified in INCLUDE statements in the options file, and the number of users are limited to <i>num_lic</i> , or the number specified in =n.
VENDOR_STRING="..."	This is a custom value defined by the software publisher and enclosed in double quotes.
VM_PLATFORMS= [PHYSICAL VM_ONLY]	Deprecated. Restricts feature usage to virtual machines (VM_ONLY) or to physical machines (PHYSICAL). If this keyword is not present, FlexEnabled applications can be run on both physical and virtual machines (default behavior).

Examples

```
FEATURE sample_app sampled 2.300 31-dec-2020 20          SIGN="<...>"
INCREMENT f1 sampled 1.000 permanent 5                HOSTID=INTERNET=195.186.*.* NOTICE="Licensed to \
Sample corp" SIGN="<...>"
```

Optional Keywords Defined by the License Administrator

The following attributes listed in [Table 3-5](#) are optional and are under control of the license administrator. These attributes have a *keyword=value* syntax where *keyword* is in lowercase.

Table 3-5 • Optional Feature Line Attributes

Attribute	Description
asset_info=" . . . "	Additional information provided by the license administrator for asset management.
dist_info=" . . . "	Additional information provided by the software distributor.
sort=nnn	Specifies sort order of license file lines. See Sort Rules .

Table 3-5 • Optional Feature Line Attributes

Attribute	Description
<code>user_info=" . . . "</code>	Additional information provided by the license administrator.
<code>vendor_info=" . . . "</code>	Additional information provided by the software publisher.

Character Limitations in Keyword Values

In places where a keyword value in a `FEATURE` or `INCREMENT` line is a string surrounded with double quotes ("..."), the string can contain any characters except the following:

- Single or double quotes (within the surrounding double quotes)
- The backslash character sequence: `\` (space+backslash+space)
- The double-backslash character sequence: `\\` (space+backslash+backslash+space)

Sort Rules

Feature definition lines are automatically sorted when they are read from the license file. The default sorting rules are as follows:

1. License file. Automatic sorting does not occur across files in a license search path.
2. Feature name.
3. `FEATURE` before `INCREMENT`.
4. Uncounted before counted.
5. Version, earlier versions before later versions.
6. Issued date, in reverse order, newest first. The date is taken from `ISSUED=` or `START=`.
7. Original order is otherwise maintained.

To turn off automatic ordering, add `sort=nnn` to the feature definition line, where `nnn` is the same on all lines; `nnn` specifies the relative sort order. The default sort order value is 100. Lines with a sort order value of less than 100 are sorted before all lines without this attribute, and lines with a sort order value greater than 100 appear after all unmarked lines. All lines with the same number are sorted as they appear in the file.

Changes in FEATURE and INCREMENT Line Format

The following lists the significant changes in the format of feature definition lines and when additional keywords were introduced.

- Version 7.1 and earlier feature definition line format uses `License_key`:

```
{FEATURE|INCREMENT} feature vendor feat_version exp_date \  
num_lic [optional_attributes] SIGN="<...>"
```

The version 7.1 and earlier format is understood by the current release.

- The `SIGN=` keyword introduced in the version 7.1.
- For version 7.1 through version 8.0 client libraries and vendor daemons, the feature definition line must have a `SIGN=` signature and, for backward compatibility with version 8.1 and earlier, can contain a `license_key`:

```
{FEATURE|INCREMENT} feature vendor feat_version exp_date \
    num_lic [license_key] [optional_attributes] SIGN="<...>"
```

- `license_key` obsoleted in version 8.1 client library and vendor daemon
- The keyword “permanent” for `exp_date` introduced in version 6 client library.
- The keyword “uncounted” for `num_lic` introduced in version 6 client library.
- `BORROW` keyword introduced in version 8.0 client library and vendor daemon.
- `FLOAT_OK` keyword introduced in version 8.0 client library and vendor daemon.
- `TS_OK` keyword introduced in version 8.0 client library and vendor daemon.
- `AUTH` keyword introduced in version 10.8 client library and vendor daemon.

PACKAGE Lines

The purpose of the PACKAGE line is to support two different needs:

- To license a product SUITE, or
- To provide a more efficient way of distributing a license file that has a large number of features, which largely share the same FEATURE line arguments.

A PACKAGE line, by itself, does not license anything—it requires a matching feature definition line to license the whole package. A PACKAGE line is shipped by your software publisher with a product, independent of any licenses. Later, when you purchase a license for that package, one or more corresponding feature definition lines enable the PACKAGE line.

Example

```
PACKAGE package vendor [pkg_version] COMPONENTS=pkg_List \
    [OPTIONS=SUITE] [SUPERSEDE=["p1 p2 ..."]] [ISSUED=date]
    SIGN="<...>"
```

Table 3-6 lists the PACKAGE line fields. They must appear in the order listed.

Table 3-6 • PACKAGE Line Fields

Field	Description
<i>package</i>	Name of the package. The corresponding feature definition line must have the same name.
<i>vendor</i>	Name of the vendor daemon that supports this package.
<i>pkg_version</i>	Provide the version of the package. The corresponding feature definition line must have the same version.

Table 3-6 • PACKAGE Line Fields

Field	Description
COMPONENTS= <i>pkg_List</i>	<p>List of package components. The format is:</p> <pre>feature[:version[:num_Lic]]</pre> <p>Packages must consist of at least one component. Version and count are optional, and if left out, their values come from the corresponding feature definition line. <i>num_Lic</i> is only legal if OPTIONS=SUIE is not set—in this case the resulting number of licenses is <i>num_Lic</i> on the COMPONENTS line multiplied by the number of licenses in the feature definition line. Examples:</p> <pre>COMPONENTS="comp1 comp2 comp3 comp4" COMPONENTS="comp1:1.5 comp2 comp3:2.0:4"</pre>
OPTIONS=SUIE	<p>Optional field. Used to denote a package suite.</p> <p>If set, the corresponding feature of the same name as the package is checked out in addition to the component feature being checked out.</p> <p>If not set, then the corresponding feature of the same name as the package is removed once the package is enabled; it is not checked out when a component feature is checked out.</p>
OPTIONS= SUIE_RESERVED	<p>Optional field. If set, reserves a set of package components. Once one package component is checked out, all the other components are reserved for that same user.</p>
SUPERSEDE [=" <i>p1 p2 ...</i> "]	<p>Optional field. Used in conjunction with ISSUED date. Replaces all PACKAGE lines for the same package name with previous or no ISSUED dates.</p>
ISSUED= <i>dd-mmm-yyyy</i>	<p>Optional field. Used in conjunction with SUPERSEDE in the PACKAGE line. Replaces all PACKAGE lines for the same package name with previous or no ISSUED dates.</p>
SIGN= <i>sign</i>	<p>SIGN= signature to authenticate this FEATURE line.</p>
or AUTH=...	<p>If your publisher has deployed his vendor daemon using the common vendor daemon technology, signatures are embedded within the AUTH= keyword. Contact your publisher for further details.</p>
	<p> Note • <i>Common Vendor Daemon is now deprecated.</i></p>

Examples

```
PACKAGE suite sampled 1.0 SIGN="<...>" \
    COMPONENTS="comp1 comp2" OPTIONS=SUIE
FEATURE suite sampled 1.0 31-dec-2020 5 SIGN="<...>"
```

This is a typical **OPTIONS=SUIE** example. There are two features, "comp1" and "comp2," which are each version 1.0, each with five licenses available. When "comp1" or "comp2" is checked out, "suite" is also checked out.

```
PACKAGE suite sampled 1.0 SIGN="<...>"\
  COMPONENTS="apple:1.5:2 orange:3.0:4"
FEATURE suite sampled 1.0 31-dec-2020 3 SN=123 SIGN="<...>"
```

In this example, the component version overrides the feature version, and the number of licenses available for any component is the product of the three licenses for "suite" and the number of licenses for that component. The result is equivalent to:

```
FEATURE apple sampled 1.5 31-dec-2020 6 SN=123 SIGN="<...>"
FEATURE orange sampled 3.0 31-dec-2020 12 SN=123 SIGN="<...>"
```



Note • The following lists changes to PACKAGE lines:

- Ability to store **PACKAGE** lines in separate files introduced in version 6 client library.
- `pkg_version` field required is mandatory.
- `AUTH` keyword introduced in version 10.8 client library and vendor daemon.

UPGRADE Lines

```
UPGRADE feature vendor from_feat_version to_feat_version \
  exp_date num_lic [options ... ] SIGN="<...>"
```

All the data is the same as for a FEATURE or INCREMENT line, with the addition of the `from_feat_version` field. An UPGRADE line removes up to the number of licenses specified from any old version (\geq `from_feat_version`) and creates a new version with that same number of licenses.

For example, the two lines provide three version 1.0 licenses of **f1** and two version 2.0 licenses of **f1**.

```
INCREMENT f1 sampled 1.000 31-dec-2020 5 SIGN="<...>"
UPGRADE f1 sampled 1.000 2.000 31-dec-2020 2 SIGN="<...>"
```

An UPGRADE line operates on the closest preceding FEATURE or INCREMENT line with a version number that is \geq `from_feat_version`, and $<$ `to_feat_version`.

Order of Lines in the License File

The order of the lines in a license file is not critical. They are sorted when they are processed so that in most cases the optimal result is achieved. However, version 7.0 and earlier versions of FlexEnabled applications and license servers implicitly impose an ordering to license file lines. Note the following suggestions for ordering lines in the license file:

- Place FEATURE lines before INCREMENT lines for the same feature.

The rules regarding FEATURE lines include the following: 1) only the first counted FEATURE line is observed by the license server, and 2) if both a FEATURE line and INCREMENT lines exist, the FEATURE line must appear first.

- Where multiple counted FEATURE lines exist for the same feature, make sure the desired FEATURE line appears first.

All but the first is ignored.

- Place node-locked, uncounted lines before floating lines for the same FEATURE. Otherwise, it is possible the floating license is consumed instead of the node-locked license, resulting in denial for other users.

- The placement of a USE_SERVER line affects behavior. A USE_SERVER line is recommended. Normally, the USE_SERVER line is placed immediately after the SERVER line. However, place any uncounted licenses not served by SERVER before the USE_SERVER line. Make sure each user that needs the uncounted license has direct access to a current copy of the file. The advantage to placing USE_SERVER right after the SERVER line is users don't need up-to-date copies of the license file.

See Also[Sort Rules](#)

Chapter 3 Reading a License File

Order of Lines in the License File

4

Locating Licenses

This section covers various topics that are related to the ability of FlexEnabled applications to locate licenses. The following are described:

- Determining a location for license files on a license server
- Configuring the machine where the FlexEnabled application is running to access licenses.

Determining the Location of the License File

Software publishers often recommend a specific location for your license file. You have the following options for making your licenses available to all systems:

- Place the license file in a partition which is available to all systems in the network that need it.
- Copy the license file to each of the individual systems.
- Set the `LM_LICENSE_FILE` or `VENDOR_LICENSE_FILE` (where `VENDOR` is the vendor daemon name) environment variable on the machines where the FlexEnabled applications are running to access license files or license servers. For details see [Setting the License Search Path Using an Environment Variable](#).

Do not choose a location for a license file where the path to the license file contains the @ symbol. The @ symbol is used to identify a license server as illustrated in [Table 4-1](#).



Note • A directory path that contains an @ symbol results in an error.

Since the vendor daemon keeps track of license usage, and since the license file contains encrypted data to protect it against modification, you may move and copy the license file as much as necessary.

On Windows, if the application cannot find the license file, the user is presented with a dialog that asks the user to specify the license file location, the license server, or license fulfillment from the internet.

For counted licenses, no matter which option you choose, you must first copy `lmadmin` or `lmgrd` and the vendor daemon to a location that the FlexEnabled application can access on the network.

Setting the License Search Path Using an Environment Variable

Most applications specify a location where they expect to find the license file and install it automatically. However, you can change the license file location by setting the `LM_LICENSE_FILE` environment variable to a license search path. Wherever a license search path is specified, it can consist of one or more of the following entries. On UNIX, the license search path entries are separated by colons ':' and on Windows, the entries are separated by semicolons ';':

- The full path to the license file
- A directory containing one or more license files with a `.lic` extension
- One of the following port settings:
 - The port setting `port@host` setting, where `port` and `host` are the TCP/IP port number and host name from the `SERVER` line in the license file.
 - The shortcut specification, `@host`, if the license file `SERVER` line uses a default TCP/IP port or specifies a port in the default port range (27000–27009).
 - A three-server redundant triad. The triad is a single entry on the license search path and is specified using a comma-separated list of three `port@hosts` (for example, `port1@host1,port2@host2,port3@host3`).

Table 4-1 shows some examples of `LM_LICENSE_FILE` and `VENDOR_LICENSE_FILE` environment variable settings.

Table 4-1 • Environment Variable Specification Examples

<code>LM_LICENSE_FILE</code> or <code>VENDOR_LICENSE_FILE</code> Setting	Description
<code>40000@myserver</code>	Used where the <code>SERVER</code> line in the license file is the following: <pre>SERVER myservers 17007ea8 40000</pre> <ul style="list-style-type: none"> ● <code>host = myservers</code> ● <code>port = 40000</code>
<code>@myserver</code>	Used where the <code>SERVER</code> line in the license file is the following: <pre>SERVER myservers 17007ea8</pre> <ul style="list-style-type: none"> ● <code>host = myservers</code> ● <code>port = None</code> specified. A default TCP/IP port number in the range of 27000-27009 is used.
<code>C:\licenses;</code> <code>40000@host1,40000@host2,40000@host3</code>	License search path on a Windows system. Unserved licenses are stored in <code>C:\licenses</code> ; served licenses are obtained from the three-server redundant triad <pre>40000@host1,40000@host2,40000@host3.</pre>

Table 4-1 • Environment Variable Specification Examples

LM_LICENSE_FILE or VENDOR_LICENSE_FILE Setting	Description
licenses:40000@myserver:40000@mybackupserver	License search path on a UNIX system. Unserved licenses are stored in the local directory licenses; served licenses are obtained from either myservers or mybackupserver. In the first instance, a license is requested from myservers; if this fails, mybackupserver is tried.

Applications accept an environment variable (or Windows Registry) named VENDOR_LICENSE_FILE, where VENDOR is the vendor daemon name, for example, DEMO_LICENSE_FILE. This environment variable's scope is limited to just those applications from software publisher using the VENDOR name.

With lmgrd and lmutil (lmstat, lmdown, and so on), the -c option overrides the setting of the LM_LICENSE_FILE environment variable.



Note • Some applications do not recognize the LM_LICENSE_FILE environment variable. FlexEnabled Java applications, in particular, do not recognize it.

Order of Searching for a License

A FlexEnabled application looks for a license file as follows:

1. When the VENDOR_LICENSE_FILE environment variable has been set for the publisher of the application, then items in the license search path set in this environment variable are searched in order.
2. The items in a license search path set in the LM_LICENSE_FILE environment variable are searched in order.
3. When any license file specified in a license search path contains a USE_SERVER line, then a license is requested from the license server specified in the SERVER line. Any FEATURE and INCREMENT lines entries after the USE_SERVER line in the license file are ignored.
4. When the environment variables are not set and the FlexEnabled application does not specify the location of the license, then the following default locations are searched:
 - On UNIX - **/usr/local/flexlm/licenses/license.dat**
 - On Windows - **C:\flexlm\license.dat**

When licenses are held in trusted storage on the same machine as the FlexEnabled application, normally the publisher will have configured the application to search local trusted storage first and then look for license files as previously described.

See Also

[Managing Multiple License Files](#) for more information about LM_LICENSE_FILE.
[Environment Variables](#)
[Ensuring License Availability](#)

Chapter 4 Locating Licenses

Setting the License Search Path Using an Environment Variable

5

Managing License Files

This section describes how license files may be modified. For detailed information about modifications required when combining license files see [Managing Licenses from Multiple Software Publishers](#).

Modifying License Files

License files usually begin with a SERVER line (or three lines for three-server redundant servers) followed by one or more VENDOR lines, followed by one or more FEATURE or INCREMENT lines. In some cases, the license file requires no SERVER line and no VENDOR line.

You can modify these elements in the license file:

- Host names on the SERVER lines
- TCP/IP port numbers on the SERVER lines (useful for firewall support)
- Three-server redundant configuration for a set of SERVER lines
- Paths on the VENDOR lines
- Options file paths on the VENDOR lines
- Optional TCP/IP port numbers on the VENDOR lines (useful for firewall support)
- USE_SERVER line
- Values in keyword=value pairs on FEATURE lines, if *keyword* is specified in lowercase

Use the \ line-continuation character to break up long lines.

Configuring the Port Used by the License Server

The port used by the license server can be specified in the license file used to start the license server. This method is the only way to configure the port setting when `lmgrd` is used as the license server manager. When using `lmadmin` as the license server manager, the port can be configured directly using the `lmadmin` user interface or the `lmadmin -licPort` command-line option.



Task ***To configure the port using lmgrd***

1. Add the port number to the SERVER line as illustrated in the following example SERVER line:

SERVER pat 17003456 **2837**

where pat is the host name of the license server machine, 17003456 is the hostid of the license server machine and 2837 is the TCP/IP port number used by the license server.

2. Use the license file that contains the SERVER line that includes the port number to start lmgrd.

Hostids for Supported Platforms

FlexNet Publisher uses system identifiers, called *hostids*, to node-lock licenses to a machine. The system identifiers may be system specific. For example, all Sun Microsystems systems have a unique hostid.

Hostid Formats

Numeric, 32-bit hostids are normally used in hexadecimal format. On some systems, the system command returns the ID in decimal format. Use a **#** character before the hostid to indicate a decimal number. For example, if the system command returns 2005771344, FlexNet Publisher accepts **#2005771344**. Alternatively, convert the decimal value to hexadecimal.

Obtaining System Hostids

The `lmhostid` utility prints the exact hostid that FlexNet Publisher requires on any given system. If your hostid contains characters other than the ASCII A through Z, a through z, or 0 through 9, use the `-utf8` option with `lmhostid`. To view a correct representation of the resulting hostid, use a utility, such as Notepad, that can display UTF-8 encoded strings.

`lmadmin` displays hostids available for the license server on the System Information tab.



Note • For the following cases, do not use the System Information tab in the `lmadmin` user interface to obtain hostids. Instead, use the methods described in the [Hostid Procurement Methods](#) table.

- **When the license server is operating on a virtual machine but bound to the physical hardware**—A limitation in `lmadmin` causes the System Information tab to show virtual machine values for Host Name, Host Domain Name, IPv4 Address, IPv6 Address, Ethernet Address, and Volume Serial Number rather than the physical machine values.
- **When running license clients or a license server in an Amazon EC2 environment**—At this time, the System Information page is unable to show hostids specific to the Amazon EC2 environment.

The following table lists some sample `lmhostid` and alternate methods to obtain the required hostid for each system architecture. FlexNet Publisher also supports a group of special hostids and vendor-defined hostids.

Table 6-1 • Hostid Procurement Methods

Hardware Platform	Hostid	Type this command	Example hostid
AIX (RS/6000, PPC)	32-bit hostid	lmhostid As best practice it is recommended to use <code>lmhostid</code> and that most of the time, the <code>uname</code> rule applies. uname -m For example, returns 000276513100. Remove last two digits and use remaining last eight digits.	02765131
HP (32-bit and 64-bit non-Itanium platforms)	32-bit hostid	lmhostid or uname -i Convert returned value to hex, or prepend with #.	778DA450 or #2005771344
HP (64-bit Itanium)	machine identification	lmhostid or getconf CS_PARTITION_IDENT Prefix returned value with "ID_STRING="	ID_STRING=9c766319-db72-d411-af62-0060b05e4c05
OS X	Ethernet address	lmhostid -ether	000A277EA17E
		 Note • This command lists the available in built Ethernet addresses, active or inactive. It does not currently list Ethernet addresses from removable devices such as USB Ethernet adapters.	
		/sbin/ifconfig enx where enx is the Ethernet interface name (with x a value from 0 to 9); remove colons from returned value.	000A277EA17E
	FlexNet ID USB port dongle	lmhostid -flexid <code>lmhostid -flexid -long</code>	FLEXID=9-b28520b9

Table 6-1 • Hostid Procurement Methods

Hardware Platform	Hostid	Type this command	Example hostid
Linux	Ethernet address	<code>lmhostid -ether</code>	00400516E525
<hr/> <div style="text-align: center;"></div> <p>Note • This command lists all available Ethernet addresses (active or inactive), including those for team-bonding virtual adaptors.</p> <hr/> <p><code>/sbin/ifconfig <ethernet_name></code> 00400516E525</p> <p>where <ethernet_name> is one of these Ethernet interface names:</p> <ul style="list-style-type: none"> • ethx • Other name type (for example, p3p4) • bond0 (for a team-bonding virtual adaptor) <p>Remove colons from returned HWaddr.</p>			
FlexNet ID USB port dongle		lmhostid -flexid <code>lmhostid -flexid -long</code>	FLEXID=9-b28520b9
<hr/> <div style="text-align: center;"></div> <p>Note • The commands <code>lmhostid -flexid</code> is to fetch the dongle id and <code>lmhostid -flexid -long</code> command is used to get the error or log information along with the dongle id.</p> <hr/>			
UUID (Universally Unique Identifier) for virtual machines		Supported for Xen, VMware, Oracle VirtualBox or Hyper-V (recommended), Parallels, QEMU-KVM, Google Compute, Microsoft Azure.	VM_UUID=DF440538-8EB7-11DC-BBDA-FE7FE89E000F
<hr/> <div style="text-align: center;"></div> <p>Note • Obtaining this hostid requires that the FlexNet Licensing Service be installed. To do this, certificate-only customers need to ensure "<code>install_fnp.sh --cert</code>" is run from the publisher directory with root-privilege at install time.</p> <hr/>			

Table 6-1 • Hostid Procurement Methods

Hardware Platform	Hostid	Type this command	Example hostid
	AMZN_EIP in Amazon EC2 environment The FlexNet Licensing Service must be running to access this hostid.	lmhostid -ptype AMZN -eip	AMZN_EIP=184.72.45.35
	VM_UUID in Amazon EC2 environment	lmhostid -ptype VM-uuid	VM_UUID=i-7d409db1 (Server only)
Sun	32-bit hostid	lmhostid or hostid	170a3472
	ethernet address	lmhostid -ether	00400516E525
Windows	Ethernet address	lmhostid	00B0A9DF9A32
		 Note • This command lists all available Ethernet addresses (active or inactive), including those for team-bonding virtual adaptors.	
	Disk serial number	DIR C: (look for Volume Serial Number is and remove -)	DISK_SERIAL_NUM=3e2e17fd
	FlexNet ID parallel or USB port dongle	lmhostid -flexid lmhostid -flexid -long	FLEXID=9-b28520b9
		 Note • For parallel port dongles, the parallel port must be configured in bi-directional mode. The commands <code>lmhostid -flexid</code> is to fetch the dongle id and <code>lmhostid -flexid -long</code> command is used to get the error or log information along with the dongle id.	

Table 6-1 • Hostid Procurement Methods

Hardware Platform	Hostid	Type this command	Example hostid
Windows (continued)	UUID (Universally Unique Identifier) for virtual machines	Imhostid -ptype VM -uuid where <virtual machine type> is one of these: Supported for Xen, VMware, Oracle VirtualBox or Hyper-V (recommended), Parallels, QEMU-KVM, Google Compute, Microsoft Azure.	VM_UUID=DF440538-8EB7-11DC-BBDA-FE7FE89E000F (Server Only)
	AMZN_EIP in Amazon EC2 environment	Imhostid -ptype AMZN -eip	AMZN_EIP=184.72.45.35

Special Hostids

FlexNet Publisher contains a number of special hostid types that apply to all platforms. These hostid types are valid to use in both SERVER lines and FEATURE lines, wherever a hostid is required.

Table 6-2 • Special Hostid Types

Hostid	Description
ANY	Locks the software to any system (meaning that it does not lock anything).
DEMO	Similar to ANY , but only for use with uncounted FEATURE lines.
COMPOSITE= <composite_ hostid>	Locks the software to a composite hostid. A composite hostid is a hashed 12-character hexadecimal value formed by combining the values of one or more simple hostids types, as defined by the software publisher. Note that composite hostids are not returned by <code>Imhostid</code> , <code>LMTTOOLS</code> , or <code>Imadmin</code> : when composite hostids are used, the software publisher will provide a utility that determines the publisher's composite hostid. On some systems multiple composite hostids may be provided, any of which may be used to identify the system that the software is locked to.
DISPLAY= <display>	Locks the software to a display. On UNIX, <display> is <code>/dev/ttyxx</code> (which is always <code>/dev/tty</code> when an application is run in the background) or the X-Display name. On Windows, it is the system name or, in the case of a terminal server environment, the terminal server client name (version 8 or later FlexEnabled applications only)
HOSTNAME= <host>	Locks the software to computer host name <host>.

Table 6-2 • Special Hostid Types

Hostid	Description
ID=<n>	Functionally equivalent to the ANY hostid—it runs on any system. The difference is that the license is unique and is used to identify the end user. This hostid is used to lock the license server (on the SERVER line) or the FlexEnabled application (on the feature definition line). The number can have dashes included for readability—the dashes are ignored. Examples: <ul style="list-style-type: none"> ● ID=12345678 is the same as ● ID=1234-5678 is the same as ● ID=1-2-3-4-5-6-7-8
INTERNET= <IP_address(es)>	Locks the software to an Internet IP address, or group of IP addresses. Wildcards are allowed. For example, 198.156.*.* means any host with a matching INTERNET IP address. The main use is to limit usage access by subnet, implying geographic area. For this purpose, it is used on the feature definition line as a hostid lock. For more information about obtaining this hostid, see the <code>-internet</code> option for <code>lmhostid</code> .  Note • (Windows only) If a Windows machine is connected to a VPN, <code>lmhostid -internet</code> returns the virtual adapter IP address. To ensure that this command returns the physical adaptor IP address during checkouts, the user needs to perform this workaround: Run <code>regedit</code> , navigate to <code>HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\services\Tcpip\Linkage</code> , locate the <code>Bind</code> parameter, and edit the adapter order so that the physical adapter is listed first. Run <code>ipconfig/registerdns</code> to put the edit into effect.
USER=<user>	Locks the software to user name <code><user></code> . User names specified in license files cannot contain spaces.

Examples

```
FEATURE f1 demo 1.0 31-dec-2020 uncounted \  
HOSTID=FLEXID=9-a6300015f SIGN="<...>"
```

or

```
FEATURE f1 demo 1.0 31-dec-2020 uncounted \  
HOSTID=INTERNET=10.10.10.* SIGN="<...>"
```

Ethernet Hostids

The Ethernet address is used on some system architectures as the hostid. An ethernet address is a 6-byte quantity, with each byte specified as two hexadecimal digits. Specify all twelve hex digits when using an Ethernet address as a hostid. For example, if the ethernet address is `8:0:20:0:5:ac`, specify **0800200005ac** as the hostid.

Several devices with an ethernet address can be attached to a machine; some of these might be virtual devices that generate a different ethernet address each time they are activated. An example of a virtual device that might generate an ethernet address is VPN (virtual private network) software.

Some devices that have an ethernet address can be detachable from the machine. For example, a laptop plugged into a docking station uses the ethernet address of the docking station; however, when it is disconnected from the docking station, the ethernet address is no longer available. A wireless adapter also has an ethernet address and this address is not available when either the wireless adapter is removed from the machine or when the wireless adapter is disabled, but still physically attached to the machine.

When `lmhostid` returns multiple ethernet hostids, ensure that you choose a permanent or stable hostid to identify your machine.



Note • FlexNet Publisher considers the address of any team-bonding virtual adaptor (for teamed Ethernet interfaces) as a stable identifier for use as a permanent hostid.

Hostids to Support Virtualization Policy

Your software publisher may choose to enforce a Virtualization support policy using the special hostid constructs in the license file. Three hostids are available for use in license file–based license servers running inside virtual machine: `VM_UUID`, `ETHER` and `VM_GENID`.

`VM_GENID` is the Generation ID of the virtual machine and has the following restrictions:

- *Windows guests only*
- *Not used as a traditional hostid - for example, may be provided in a `VENDOR_STRING` field.*

Refer to the Virtualization white paper for the example usage of `VM_GENID`.



Note • The FlexNet Licensing Service must be installed on machines that use virtualization features.

Hostids to Support Cloud Licensing

The hostids listed in this chapter for the Amazon EC2 environment support typical use cases for licensing software in a cloud. For a description of these use cases and the hostids, see [Chapter 16, Licensing in a Cloud-Computing Environment](#).

License Models

License rights are created by the software publisher. License rights specify floating (concurrent) usage, node-locked (both counted and uncounted), or any combination of floating, counted, and uncounted.

Floating (Concurrent) Licenses

A *floating license* means anyone on the network can use the FlexEnabled application, up to the limit specified in the license file or fulfillment record (also referred to as *concurrent usage* or *network licensing*). Floating licenses have no hostids on the individual FEATURE lines. Floating licenses requires a license server manager and a vendor daemon to be running to count the concurrent usage of the licenses.

An example of a license file that provides floating licenses is:

```
SERVER lulu 17007ea8
VENDOR sampled
FEATURE f1 sampled 1.00 31-dec-2020 2 SIGN="<...>"
FEATURE f2 sampled 1.00 31-dec-2020 6 SIGN="<...>"
FEATURE f3 sampled 1.00 31-dec-2020 1 SIGN="<...>"
```

This license file specifies that two licenses for feature **f1**, six licenses for feature **f2**, and one license for feature **f3** are available anywhere on the network that can access the license server, called **lulu**. The license server manager uses one of the default TCP/IP ports.

The equivalent floating licenses are held in trusted storage as a fulfillment record that contains the same FEATURE lines as in the license file without any SERVER or VENDOR lines.

Node-Locked Licenses Using Hostid

This section describes node-locked licenses using a hostid. Licenses held in trusted storage are node-locked because trusted storage is locked to a machine, see [Locking of Licenses Using Hostid or Trusted Storage](#) for an explanation.

Node-locking means the FlexEnabled application can be used on one system or a set of systems only. A node-locked license has a hostid on the FEATURE line that identifies a specific host. There are two types of node-locked licenses: uncounted and counted.

If the number of licenses value is set to either zero (0) or uncounted, then the license will not be counted which allows the license to be used an unlimited number of times. This configuration does not require a license server because it is not necessary to count the concurrent usage of the features. The license server can be used to serve uncounted licenses. Note that served uncounted licenses are supported only with feature lines node-locked to HOSTID=ANY.

The following license file allows unlimited usage of feature **f1** on the systems with hostids of **17007ea8** and **1700ab12**:

```
FEATURE f1 sampled 1.000 31-dec-2020 uncounted HOSTID=17007ea8 SIGN="<...>"  
FEATURE f1 sampled 1.000 31-dec-2020 uncounted HOSTID=1700ab12 SIGN="<...>"
```

Alternately, these two FEATURE lines could have been issued by your software publisher with a *hostid list*:

```
FEATURE f1 sampled 1.000 31-dec-2020 uncounted HOSTID="17007ea8 1700ab12" SIGN="<...>"
```

If these were the only FEATURE lines in this license file, neither the license server manager or vendor daemon are necessary and you do not need to start one.

The following license file provides three licenses for feature **f1**, locked to the system with hostid **1300ab43**. Since the license server and licenses are locked to the same system, the daemons run on the same system that runs the FlexEnabled application.

```
SERVER lulu 1300ab43 1700  
VENDOR sampled /etc/sampled  
FEATURE f1 sampled 1.00 31-dec-2020 3 HOSTID=1300ab43 SIGN="<...>"
```

Mixed Node-Locked and Floating Licenses

Uncounted node-locked and concurrent usage licenses can be mixed in the same license file.

The following license file allows unlimited use of feature **f1** on systems **17007ea8** and **1700ab12**, while allowing two other licenses for feature **f1** to be used anywhere else on the network:

```
SERVER lulu 17001234 1700  
VENDOR sampled C:\flex1m\sampled.exe  
FEATURE f1 sampled 1.00 31-dec-2020 uncounted HOSTID=17007ea8 SIGN="<...>"  
FEATURE f1 sampled 1.00 31-dec-2020 uncounted HOSTID=1700ab12 SIGN="<...>"  
FEATURE f1 sampled 1.00 31-dec-2020 2 SIGN="<...>"
```

This configuration requires a license server manager and vendor daemon because the licenses on the third FEATURE line are counted.

Counted vs. Uncounted Licenses

The license model (as defined in the license file on the end user machine) determines whether a license server is needed. If all feature definition lines have a license count set to either zero (0) or uncounted, then the customer does not need a license server. This type of license is called uncounted. Alternatively, if any features have a non-zero license count, then the customer needs a license server to count those licenses. If a software publisher wants to use FlexNet Publisher without a license server, they must issue uncounted licenses.

The license server can serve uncounted licenses also. This is often done so that:

- Transactions can be logged into the report log for all license requests, which can then be reported on by FlexNet Manager.

- Options file constraints can be applied to the licenses.

To serve uncounted licenses from a license server, include the SERVER and VENDOR lines in the license file. The user application must point to the license server with port@host (recommended). Note that served uncounted licenses are supported only with feature definition lines node-locked to HOSTID=ANY.

Mobile Licensing

End users often want to use applications on computers that do not have a continuous connection to a license server. These situations include:

- Working on a laptop
- Using a computer both at work and at home
- Working from several different computers not connected to a license server

FlexNet Publisher supports licenses that allow one of several kinds of mobile licensing:

- Node-locked to a laptop
- Node-locked to a FlexNet ID dongle
- Node-locked to a FlexNet ID dongle with FLOAT_OK keyword
- License borrowing with BORROW keyword
- Node-locked to a user name
- Fulfilled from a prepaid license pool
- Optionally when provided by the publisher, [Distribution of Node-Locked Licenses to Networked Machines](#) using trusted storage can be used.

You should use license rehosting if an enterprise wants to move a license without using one of these methods. The software publisher must generate a new node-locked license file for each new client computer. Rehosting requires administrative overhead because the software publisher must be involved with each move.

Node-Locked to a Laptop Computer

To use a license exclusively on one laptop computer, the license should be node-locked to that computer. When the license is held in a license file, it resides on the laptop computer. Any license held in trusted storage on a laptop computer is node-locked to the laptop.

Node-locked to a FlexNet ID Dongle

To move a license between different systems, it can be locked to a FlexNet ID dongle (a dongle that connects to a parallel or USB port). You can move this license between systems by installing a copy of the license file with a hostid set to the FLEXid of the dongle on each system and moving the dongle from one system to another. Since the license is tied to the dongle, only the system with the dongle can use the license.

FlexNet ID dongles are made available by your software publisher. Your software publisher can also provide you with an installer that installs drivers for all FlexNet ID dongles.

Node-Locked to a FlexNet ID Dongle with FLOAT_OK

Because the hostid of the dongle (the FLEXID) defines the license server and the license floats on the network, this method has an advantage over simply using a license locked to a FLEXID.

The software publisher issues you a dongle; a license file with a FEATURE line node-locked to the FLEXID of the dongle and that contains the FLOAT_OK keyword. One dongle and FEATURE line containing the FLOAT_OK keyword is needed for each instance of a license that is mobile. When the dongle is attached to a license server, the license floats on the network. When the dongle is removed from the license server, the license is available only on the standalone computer.

This method supports parallel or USB dongles. Because it is simpler to attach multiple USB dongles to a computer, they may be preferable.

Using a FlexNet ID Dongle for Mobile Licensing Using a FLOAT_OK License

The software publisher provides a dongle, a dongle driver installer, and a license file that contains a FEATURE line node-locked to the FLEXID containing the FLOAT_OK keyword. A license administrator then:

1. Installs the license file on the license server.
2. Installs the FlexNet ID dongle driver on the license server.
3. Attaches the dongle to the license server.
4. Starts the license server or rereads the license file

While the dongle is attached to the license server, the node-locked license associated with it floats on the network.



Task

To transfer a license from the pool of floating licenses to a disconnected computer:

1. Copy the license file containing the FLOAT_OK node-locked FEATURE line from the license file on the license server to a license file on the client in the location where the FlexEnabled application expects to find its license file.
2. Install the dongle driver on the client computer, if it is not already installed.
3. Move the dongle matching the node-locked FEATURE line from the license server to the client. When the dongle is removed from the license server, this license is unavailable on the network.
4. Disconnect the client computer from the network. Now the license is available on the computer with the dongle, even though that computer is disconnected from the network.



Task

To return the license to the license server so it floats on the network again:

1. Remove the dongle from the client and replace it on the license server.
2. Reread the license file for the license server that serves the floating version of the license by running `lmreread`.

When the dongle is returned to the license server, the FLOAT_OK license does not float on the network again until `lmreread` is run.

FLEXID with FLOAT_OK Example

The following is a sample license file. It is shipped with two dongles: FLEXID=9-34efc1d8 and FLEXID=9-30eb7ff6.

```
SERVER myhost ANY
VENDOR sampled
FEATURE f1 sampled 1.0 permanent uncounted FLOAT_OK \
    HOSTID=FLEXID=9-34efc1d8 SIGN="<...>"
FEATURE f1 sampled 1.0 permanent uncounted FLOAT_OK \
    HOSTID=FLEXID=9-30eb7ff6 SIGN="<...>"
```

The user installs the license file and the two dongles on the license server. When attached to the license server, each uncounted FLOAT_OK license floats on the network and allows a single use. Therefore, up to two users can use **f1** on the end user's network, except on the license server itself, where the license use is disallowed.

If a user wants to work at home, the user installs a license file that contains the FEATURE line node-locked to FLEXID=9-34efc1d8 (this only needs to be done once), transfers the dongle with FLEXID=9-34efc1d8 from the license server to the client, and installs the dongle driver on the client computer (this also only needs to be done once). The user disconnects the client computer from the network and uses the transferred FLOAT_OK license on the client computer. The license server allows only the single remaining FLOAT_OK license to float on the network.

After returning the dongle to the license server, the license administrator runs `lmreread` so the returned license can float again.



Note • *FLOAT_OK* keyword introduced in version 8.0 client library, license server manager, and vendor daemon. All components must be version 8.0 or later in order to use *FLOAT_OK*.

License Borrowing with BORROW

This method of implementing mobile licensing is used only when license rights are held in license files.

If a license is to be used on a computer that is intermittently connected to a license server, that license can be issued as a floating license with the BORROW keyword. A BORROW license can be borrowed from a license server via a special checkout and used later to run an application on a computer that is no longer connected to the license server. License borrowing must be enabled by a software publisher before a user can borrow licenses.

With license borrowing, a software publisher issues a floating license with a FEATURE line that contains the BORROW keyword. A user specifies the expiration date a borrowed license is to be returned and runs the application while connected to the network which writes borrowing information on the client computer. The license server keeps the borrowed license checked out. The FlexEnabled application automatically uses the local borrowing data to do checkouts during the borrow period. If enabled by the software publisher, borrowed licenses can be returned early, that is, before the borrow period expires. Upon the earlier of either the expiration of the borrow period or the early return of a borrowed license, the local borrowing data no longer authorizes checkouts and the license server returns the borrowed license to the pool of available licenses. No clock synchronization is required between the license server and the system running the FlexEnabled application.

Initiating License Borrowing

If a software publisher has enabled license borrowing by issuing a license file that contains a FEATURE line with the BORROW keyword, an user initiates license borrowing in one of three ways:

- Using the borrowing interface in application, if provided in the application
- Running the `lmborrow` utility to set `LM_BORROW`
- Setting the `LM_BORROW` environment variable directly

Application Interface

The user initiates license borrowing this way only if the application provides a borrowing interface. Information about this is supplied by the software publisher.

Running the lmborrow Utility

`lmborrow` is one of the `lmutil/lmtools` utilities. To initiate borrowing, the user runs `lmborrow` from the command line or through `lmtools`:

```
lmborrow {vendor|all} enddate [time]
```

where *vendor* is the vendor daemon that serves the licenses to be borrowed, or `all` specifies all vendor daemons in the license server. *enddate* is the date the license is to be returned in `dd-mm-yyyy` format. *time* is optional and is specified in 24-hour format (`hh:mm`) in the FlexEnabled application's local time. If *time* is unspecified, the checkout lasts until the end of the given end date.

For example:

```
lmborrow sampled 20-aug-2017 13:00
```

Setting the LM_BORROW Environment Variable Directly

The `lmborrow` utility is a user interface to set `LM_BORROW` in either the registry (Windows) or in `$HOME/.flexlmborrow` (UNIX). `LM_BORROW` can also be set directly as an environment variable:

```
today:{vendor|all}:enddate[:time]
```

where:

Table 7-1 • `LM_BORROW` Environment Variable Arguments

Argument	Description
<i>today</i>	Today's date in <code>dd-mm-yyyy</code> format. Any checkouts done on this date create local borrow information. If a checkout is done on a different date than this date, no local borrowing information is created.
<i>vendor</i>	Vendor daemon that serves the licenses to be borrowed, or <code>all</code> specifies all vendor daemons in the license server.
<i>enddate</i>	Date the license is to be returned in <code>dd-mm-yyyy</code> format.

Table 7-1 • LM_BORROW Environment Variable Arguments

Argument	Description
<i>time</i>	Optional. <i>time</i> is specified in 24-hour format (<i>hh:mm</i>) in the FlexEnabled application's local time. If <i>time</i> is unspecified, the checkout lasts until the end of the given end date.

For example:

```
LM_BORROW=15-aug-2017:sampled:20-aug-2017:13:00
```

In this example, one or more licenses served by the `sampled` vendor daemon are borrowed on August 15, 2017, and are scheduled to be returned at 1 P.M. on August 20, 2017.

Borrowing a License

To borrow a license for a desired feature, *on the same day and the same system* that the user runs `lmborrow` or sets `LM_BORROW` (and while still connected to the network), the user runs the application to check out and borrow the license. If the user runs the application more than once that day, no duplicate license is borrowed. No license is borrowed if the application is run on a day different than the date borrowing was set to be initiated.

For example, say that today you want to borrow a license for the PageWizard feature for a week. The PageWizard feature is served by the `sampled` vendor daemon. Today, while you are connected to the network, run `lmborrow` or set `LM_BORROW` directly. For example:

```
lmborrow sampled enddate
```

Today, after you run `lmborrow`, while you are connected to the network, run the application that checks out a license for the PageWizard feature. After the license is checked out, close the application and disconnect your system from the network. The license that you just checked out stays checked out from the license server until the borrow period expires—that license now is used on your disconnected system until the borrow period expires. Once checked out, it remains checked out for the full borrow period. The borrow period cannot be renewed until the period has expired.

Clearing the Borrow Period

Once you have borrowed all the licenses that you need for the current borrow period (defined by the `LM_BORROW` environment variable), prevent licenses for any additional features from being borrowed by running `lmborrow -clear`. This clears the `LM_BORROW` setting in the registry (Windows) or `$HOME/.flexlmborrow` (UNIX). `lmborrow -clear` does *not* clear the local information about licenses you have already borrowed.

Checking Borrow Status



Task *To print information about borrowed features:*

1. Issue the following command on the system from which they are borrowed:

```
lmborrow -status
```

The system that borrowed the features does not have to be connected to the network to determine the status.

Returning a Borrowed License Early



Task

To return a borrowed license before the borrow period expires:

1. Reconnect the borrowing system back to the network.
2. From the same system that initiated the borrowing, issue the command:

```
lmborrow -return [-c licfile] [-d display_name] [-u username] [-h hostname] [-fqdn] [-vendor name] feature [-bv version]
```

This option may or may not be allowed by your software publisher. Check directly with your software publisher to determine if they support borrowed licenses being returned early.

The option `-bv[version]` is used to return a particular version of a feature.

Support for License Borrowing

See the following sections for more information about the utilities and keywords in the options file that support license borrowing:

- [lmborrow](#) utility
- [lmdown](#) utility
- [lmstat](#) utility
- [BORROW_LOWWATER](#) keyword
- [EXCLUDE_BORROW](#) keyword
- [INCLUDE_BORROW](#) keyword



Note • *BORROW* keyword introduced in version 8.0 client library, license server manager, and vendor daemon. All components must be version 8.0 or later in order to use *BORROW*.

Node-locked to a User Name

This method of implementing mobile licensing is used only when license rights are held in license files.

If a license is to be used exclusively by one user on different systems, that license can be node-locked to the user's user name. The license file is copied to the different systems on which the user might work; the user's user name must be identical on each system. For this method to be useful, individual user names in an organization must be unique. Note that a user name, when used in a license file in this way, cannot contain spaces.

Fulfilled from a Prepaid License Pool

In this method, the user buys a prepaid number of license-days from the software publisher. The user can then fulfill a license using a partial amount of the total license-days for the given borrow period, node-locked to a particular system. For example, in preparation for a business trip (or even during a business trip), the user fulfills a license that

expires in five days that is node-locked to their laptop. Each fulfillment can be node-locked to a different system (or even multiple times to the same system), thus allowing mobility of license usage within the pre-paid number of license-days.

This model is like pay-per-use because each fulfillment is made from a decreasing number of license-days. It is different than other pay-per-use models because, once node-locked to a system, that system is allowed unlimited use of the application until the license expires. This short-term license cannot be returned early; once fulfilled, those license-days cannot be refunded. Other pay-per-use models charge based on the number of times the application is used.

Selecting a License Server Machine

When selecting a machine on which to install a license server, select a stable system; do not choose systems that are frequently rebooted or shut down. Normally, it is not required that each system be the same architecture or operating system as other license servers or the client machines on which the FlexEnabled applications are running.

The following sections discuss the resources used by the license server. When you select a machine on which to install a license server, you may need to consider whether it has sufficient resources. For small numbers of licenses (under about 100), most of these system limits are not a problem on any workstation.

License Server Sockets

When using TCP/IP ports, each FlexEnabled application connected to a license server uses one or more sockets. Depending on how the publisher implemented licensing, the FlexEnabled application may need one or more sockets. Ask the publisher for this information. The per-process system limit for file descriptors determines the number of sockets available to the license server. The total number of sockets that the license server uses is slightly larger than the total number needed by the FlexEnabled applications that connect to it.

If the number of sockets required by the license server on a single system becomes excessive, then one solution is to run multiple license servers and split the licenses between them. This reduces the networking traffic to each license servers [Redundancy Using the License Search Path](#) for instructions and information about this configuration. Your publisher will need to agree to issue new license files, if you want to move licenses from an existing license server. If the licenses are held in trusted storage, the publisher may provide an automated process for returning them and activating them on another license server.

License Server CPU Time

For small numbers of clients, the license servers use very little CPU time. The servers might have consumed only a few seconds of CPU time after many days.

For a large number of clients (where each are exchanging heartbeat messages with the license server), or for high checkout and checkin activity levels (hundreds per second), the amount of CPU time consumed by the server may start to become significant; although, even here, CPU usage is normally not high. In this case, you may need to ensure that the system you select has enough CPU cycles to spare.

License Server Disk Space

The only output files created by the license servers are the debug and report log files. FlexNet Manager, Flexera Software's Web-based software license management system, uses the report log files to generate accurate usage reports. If there is a lot of license activity, these log files grow very large. You need to consider where to put these files and how often to rotate and archive them. You have the option to suppress log file output if disk space is at a premium.

It is recommended that the log files are local files on the server systems to avoid networking dependencies.

See Also

[Report Log File](#)

[Debug Log File](#)

License Server Memory

The license server uses little memory. The vendor daemons use approximately 2 MB each, although memory usage increases in the vendor daemon with the number of concurrent licenses, size of the options file, and the number of concurrent users. `lmadmin`, uses between 7 and 10 MB of memory during typical usage. Typically, the command-line license server manager, `lmgrd`, uses approximately 2 MB.

Network Bandwidth for License Server

FlexNet Publisher sends relatively small amounts of data across the network. Each transaction, such as a checkout or checkin of a license, generally transfers less than 1 KB of data. This means that FlexNet Publisher can be effectively run over slow networks (such as dial-up SLIP lines) for small numbers of clients.

For a large number of FlexEnabled applications (hundreds), each of which exchange heartbeat messages with the vendor daemon, the network bandwidth used may become significant. In this case, run the FlexEnabled application and server on the same local area network, and run multiple license servers if required. Users can use a license search path in the `LM_LICENSE_FILE` environment variable to have effective access to both servers. Enterprises can experience a performance issue when there is slow network communication or if FlexEnabled clients are using a dial-up link to connect to the network.

When you are using `lmadmin`, which uses HTTP, you need to consider the clients that connect to the `lmadmin` user interface. Depending on the number of clients and the frequency of the page refresh, they can impose a significant burden on network traffic.

License Server Locally Mounted Disks

It is recommended that you do not use remote mounted disks when you run the license server. In other words, it is recommended that `lmadmin` or `lmgrd`, the vendor daemons, the license file, and the debug and report log files are all on locally mounted disks. If any of these files are on a remote mounted disk, this doubles the points of failure, which could lead to a temporary loss of all of your licenses. When all files are mounted locally, the licenses are available as long as the server is running. When the files are on a different system, licenses may become unavailable if the license server or file server fails.

License Server Port

It is recommended that a specific port is designated on the license server machine to be used only by license server components. The benefits of this are that it is:

- Easy to track processes by the port that they are run on.
- Easier to configure FlexEnabled clients to access the license server.
- Easier to manage license server components in an environment where a firewall and/ or antivirus software is in use.
- Useful in preventing port conflicts and the hijacking of the port by other processes.

To configure the license server port:

Using Imgrd - Specify it in the license file used to start the license server; see [Configuring the Port Used by the License Server](#).

Using Imadmin - Configure the license server manager port either:

- Using the Imadmin user interface. See the online help for information.
- Using the Imadmin -licport command. For information about the -licport argument, see [Imadmin Command-line Arguments](#).

Running the License Server in a Cloud

Operating in a public or virtual private cloud in an Amazon EC2 environment, you can run the license server on an AMI instance and then deploy instances of the FlexEnabled application as one or more license clients in the cloud, in your enterprise network, or in both, with all clients pointing to the license server in the cloud.

In a public cloud, you can run Imhostid directly on the AMI instance containing the license server to obtain the hostid needed to bind the license. . For more information about these use cases and the required hostids, see [Chapter 16, Licensing in a Cloud-Computing Environment](#).

Chapter 8 Selecting a License Server Machine

Running the License Server in a Cloud

License Server Manager “Imadmin”

The *license server manager* is one of the components that makes up a license server (the other being the vendor daemon). It handles the initial contact with FlexEnabled applications, passing the connection on to the appropriate vendor daemon. The purpose of the license server manager is to:

- Start and maintain vendor daemons as required for serving license rights from different software publishers.
- Refer application checkout (or other) requests to the correct vendor daemon.

There are two versions of the license server manager:

- **Imadmin**—The Web-based license server manager
- **Imgrd**—The original license server manager with a command-line interface

This section describes Imadmin. For information about Imgrd, see [License Server Manager “Imgrd”](#).

Imadmin provides improved methods of managing the license server and vendor daemons. A brief description of the improved capabilities follows. For a more detailed comparison of Imgrd and Imadmin, see [Migrating from Imgrd to Imadmin](#).

Imadmin Capabilities

- **Direct configuration of the vendor daemons and license server manager**—License-server port number, vendor-daemon path and port, and three-server redundant port can be configured without any edits to the license files.
- **Configurable alerts**—You can set up Imadmin to issue alerts to warn you of potential problems (for example, license expiry, no available licenses, or vendor daemon status).
- **License rights status display**—The Imadmin user interface provides a display of all available and in-use license rights. This display can include all concurrent (floating) licenses both from license files and from trusted storage. It can also include activatable and hybrid licenses (held in trusted storage) when these are available on the license server.
- **Command-line functions accessed by option buttons**—For example, the **Stop Server** and **Reread License Files** buttons perform the same actions as the Imdown and Imreread functions, respectively. For a list of license administration functions that are available directly from Imadmin, see [Imadmin License Administration Functions](#).

- **Minimal editing of license files**—Option file specification requires editing.

This release of ladmin is available for use on a limited number of platforms. For full details, contact your software publisher or see the Flexera Software download site. ladmin is compatible with licensing components from version 9.2 or later. See [Version Compatibility Between Components](#) for detailed information on how to determine what versions of the licensing components are provided in your licensed applications.

Downloading and Installing ladmin

This section contains instructions for downloading and installing the ladmin license server.

System Requirements for ladmin

For information on supported platforms and Web browsers of ladmin see the latest *Release Notes*.

For non-Windows 64-bit platforms, use the 32-bit ladmin installer. For Windows, the 32-bit installer can be used for 32-bit and 64-bit Windows platforms.

The ladmin installer requires that JRE 1.6 or later (for OS X: JRE 1.7 or later) is installed. If the JRE is not already present on the machine, it must be installed separately, because it is not bundled with the ladmin installer.



Note • If you want to use a different JRE version while installing/uninstalling you can use the LAX_VM command, as follows:

```
C:\Users\fnpauto\Desktop>ladmin-i86_n3-11_14_1_1.exe LAX_VM "C:\Program Files\Java\jre1.8.0_112\bin\java.exe"
```

Additional Installation Requirements

ladmin has these additional requirements:

- Linux 32-bit libraries, required by ladmin, are not automatically installed with RedHat Enterprise Linux 6 (64-bit). You must manually install these libraries on this operating system. Refer to the RedHat Enterprise Linux documentation for details.
- To use ladmin on Windows platforms, the Microsoft Visual C++ 2008 Redistributable Package (x86) must be installed. You have an option to install this package during the FlexNet Publisher License Server installer process.

Using the License Server Installer

Download the FlexNet Publisher ladmin installer from Flexera Software’s website; or, if the software publisher has provided their own ladmin installation program, locate that program. If you have an existing installation of the ladmin license server, see [Upgrading ladmin](#) on page 77 for instructions. This section describes how to install the license server for the first time.

Whether running the FlexNet Publisher ladmin installer or the software publisher’s version of the ladmin installer, accept the default settings whenever possible. If you are given the option to modify installation settings, keep the following information in mind. (This information refers mainly to Windows and options in the FlexNet Publisher ladmin installer, but you can apply the information to the software publisher’s installation program as well.)


- **Choose Install Folder window**—Do not install the ladmin license server in the same folder as an existing FlexNet Publisher installation. Choose a new or an empty folder as the installation directory.

The default path is **C:\Program Files (x86)\FlexNet Publisher License Server Manager**.

- **Choose Data Folder window**—(Windows only) The installer creates the ladmin service of the type “Local Service”, with start-up type “Automatic”. If the service is started with a non-admin account, it does not have sufficient privileges to modify the contents of the **Program Files (x86)** directory. It is therefore strongly recommended installing the folders that are updated during run time (**conf, logs, cache, licenses**) under **ProgramData**. The default path is **C:\ProgramData\FLEXlm\ladmin**.
- **Import Files from Previous Installation window**—(Windows only) If you want to import license files, log files, configuration data, and vendor daemons from a previous installation of the ladmin installer, provide the previous installation paths. For more information, see [Upgrading ladmin](#) on page 77.
- **Service Configuration window**—While it is possible to manually start and stop the ladmin license server manager, it is recommended that you install it as an operating system service so that it will automatically start whenever the operating system restarts. The installer will set up the service for you on Windows. For UNIX or Mac, see [Installing ladmin License Server Manager as an Operating System Service](#) for more details.
- **Windows Active Directory domain user or group prompt**—During installation on a Windows machine, the installer might prompt you to pre-designate an Active Directory domain user or group name to be used to sign into the ladmin user interface. (Providing this information is optional.) If you specify a domain user name, administrators can sign in using this user name and its associated password as defined in Active Directory. If you specify a domain group name, administrators can sign in using the name and password of any domain user belonging to the specified group. (Designating a domain group is helpful in a large enterprise where you might have several license administrators who need access to the interface.) Once ladmin is installed, you can use its interface to set up additional domain users or groups for sign-in.



Note • The ladmin installer of certain software publishers might provide this option to pre-designate an Active Directory user or group for sign-in. However, the FlexNet Publisher ladmin installer that you download from the Flexera Software website does not offer this option.



After installing ladmin with the default configuration, you can configure the location where it stores the license files it uses. See [Configuring the License File Upload Directory](#) for details.

- LDAP user support by ladmin on Linux**—Linux platforms support LDAP users. License administrators can create an LDAP user account as an ladmin domain-administrator-type or domain-user-type user.

The License Administrator can then log in to the ladmin user interface using the just-added LDAP user ID (and its associated password). To identify this account, use the format `domain\username`, where domain is a valid LDAP domain to where the machine running ladmin can connect, and username identifies a valid account within that domain. (Also, ladmin should have been already configured to connect to that LDAP server). This value specified for account is not case-sensitive and can include up to 64 characters. Using the ladmin user interface, you can change this account’s role to domain-administrator or domain-user or remove the account from the ladmin user-interface user list. However, you cannot manage the account as an LDAP user.



Task To configure LDAP for ladmin on Linux:

- Configure the LDAP server using the following command:

```
./ladmin -ldapHost <LDAPServerHost> -ldapPort <LDAPServerPort> -ldapUser <domain\user> -
ldapPassword <ldapUserPassword> -ldapBaseDN <BaseDN name> -noWeb -noLic
```

The above command is used to configure ladmin running on the Linux server to connect and authenticate to an LDAP server.

Table 9-1 • Parameters used by ladmin on Linux to connect to LDAP

Option	Description
ldapHost	Specify the server host name or IP address of the LDAP server
ldapPort	Specify the server port of the LDAP
ldapUser	Specify the domain user name
ldapPassword	Password of the specified domain user.
ldapBaseDN	Base Distinguished name to be used while searching for users on the LDAP server. For example: If the Active Directory server is testads.flexera.com, the BaseDN value would usually be DC=TESTADS,DC=FLEXERA,DC=COM

The “-ldapUser” and “-ldapPassword” options should be used to specify a user-account and password combination that can be used to bind to the AD server. This account/password info would be used for binding while checking for the existence of a particular domain user before adding it to the configuration file.

2. Check the configuration file (**conf\server.xml**) and start the ladmin server.
3. Log on to the ladmin web GUI as an administrator. The ladmin dashboard is displayed.
4. To add domain users, select the **Administration** tab, open the **User Configuration** tab and click **New**. The **Create User** page is displayed.
5. For **Role**, select **Domain Administrator**.
6. Enter the user name in the format *domain\user*. For example: *DOMAIN1\USER1*.
7. The new domain users can now log on to the **Administration** pages using the domain account and password.

Running the Installer in Console Mode

On AIX, Linux, Solaris, or Windows platforms, you can run the ladmin installer in console mode. This mode enables you to install ladmin from the command line, providing an alternative to the user interface–based method.

Use the following command to run the installer in console mode:

```
<ladmin_installer> -i console
```

where *<ladmin_installer>* is the name of the ladmin installation program.

The console installation process prompts you for information needed to complete the installation.

License Server Directory Structure

After installing the ladmin license server, you see that files have been installed in the following directories:

- **Program Files (x86)\FlexNet Publisher License Server Manager**—(Windows only) The installation folder that you specified on the panel **Choose Install Folder** when installing ladmin. This directory contains folders and

files that are not modified during run time; as well as **lmadmin.exe**, the license server executable. This directory is often referred to as the installation root directory (`<lmadmin_install_dir>`).

- **ProgramData\FLEXlm\lmadmin**—(Windows only) The installation folder that you specified on the panel **Choose Data Folder** when installing lmadmin. This directory contains folders with files that are updated during run time. This directory is also referred to as the runtime data directory (`<lmadmin_runtime_data_dir>`).
- **...\FNPLicenseServerManager**—(non-Windows platforms) The installation folder that you specified when installing lmadmin; often referred to in this documentation as the installation root directory (`<lmadmin_install_dir>`). Configuration paths are usually specified relative to this directory location. This directory contains lmadmin, the license server executable.

Do *not* edit the contents of any file or directory except where explicitly instructed to by this *License Administration Guide*, or by other supplied licensing documentation.

Table 9-2 • Directories used by the License Server Manager

Directory	Description of Contents
\demo	Contains sample license files and the <i>demo</i> vendor daemon. (On Windows systems, this folder is located in the installation root directory.)
\eventlog	Exists on Window systems only and includes the files needed to allow the license server to record messages to the Windows event log. (On Windows systems, this folder is located in the installation root directory.)
\examples	Contains code samples that show how to build capabilities using the Web services. (On Windows systems, this folder is located in the installation root directory.)
\uninstall	Contains the files required to uninstall lmadmin. (On Windows systems, this folder is located in the installation root directory.)
\web	Contains the license server management interface. (On Windows systems, this folder is located in the installation root directory.)
\wsdl	Contains the WSDL file that you can use to generate a client proxy for the Web services. (On Windows systems, this folder is located in the installation root directory.)
\cache	System directory that is created after you start any vendor daemon using the license server management interface. (On Windows systems, this folder is located in the runtime data directory.)
\conf	Contains server.xml and other system files that define the license server configuration. (On Windows systems, this folder is located in the runtime data directory.)

Table 9-2 • Directories used by the License Server Manager

Directory	Description of Contents
<code>\licenses</code>	Contains the license files served by Imadmin. (On Windows systems, this folder is located in the runtime data directory.)
<code>\logs</code>	Contains the application log files. This directory is created after the license server is started for the first time. (On Windows systems, this folder is located in the runtime data directory.)

Upgrading Imadmin

Before installing a new version of Imadmin:

- If you have configured Imadmin as a system service, shut down the service.
- Shut down any Imadmin processes running on the system.

The Imadmin installer provides the option **Import Files from Previous Installation**. This option enables you to upgrade Imadmin while retaining a previous Imadmin configuration.

The following files and folders are imported from an existing Imadmin installation:

- **Imadmin configuration data**—Permanent Imadmin settings that were configured either via the license server management interface or via the command-line. For example, these settings include the license server port number, vendor daemon path and port, three-server redundant port, and the maximum size of a file import. These and other configuration data are held in the file `server.xml` which is imported to the `conf` directory.
- **Vendor daemon files and license files**—The vendor daemon executable, the license file used to start the vendor daemon, and additional license files imported via the license server management interface after the initial import of a vendor daemon. A copy of the directory structure is created and these files are imported.
- **Log files**—The log file (`<vendor>.log`) for each vendor daemon.

This section describes the upgrade procedure when you are installing the latest version of Imadmin and want to import files from a previous Imadmin installation. To determine which version of Imadmin you are using, see the **Release Version** value displayed on the **System Information** page.



Task *To upgrade an existing Imadmin installation:*

1. Run the Imadmin installer.
2. In **Choose Install Folder**, set the installation root directory. Ensure that the installation root directory is not a sub-directory of the existing installation. (On Windows, the default path is `C:\Program Files (x86)\FlexNet Publisher License Server Manager`.)
3. (Windows only) In **Choose Data Folder**, set the runtime data directory. The default path is `C:\ProgramData\FLEXlm\Imadmin`.

4. In **Import Files from Previous Installation**, you can select to import data from a previous installation. To do so, select the **Import** check box and provide the path to the installation root directory of the relevant lmadmin installation.

Provide the following information:

- **Previous Installation Path**—Specify the path to the installation root directory of the lmadmin installation that you want to import.
- **Previous Data Folder Path**—(Windows only) Specify the path to the runtime data folder of the lmadmin installation that you want to import. This enables you to import data files from a previous installation.



Note • If you have uninstalled the previous lmadmin installation and saved the configuration files in a separate directory (for example, `C:\temp\<previous_installer_data>\conf\server.xml` and `C:\temp\<previous_installer_data>\logs\lmadmin.log`), specify the path to the directory that contains the **conf** and **logs** folders (`C:\temp\previous_installer_data>`).

If your previous installation did not distinguish between an installation root directory and runtime data directory, specify the path to the installation root directory in both fields.

5. If you have configured the license server manager port, in **Launch Configuration** enter the license server port number. (See [License Server Manager Not Starting](#).)
6. If you have configured the TCP/IP port that the Web server uses to listen for communication with clients connecting to the license server management interface, in **Launch Configuration** enter the HTTP port number. (See [License Server Manager Not Starting](#).)
7. Complete the remaining installation dialogs.



Note • Note the following when upgrading lmadmin:

- The lmadmin installer imports an existing vendor daemon and its associated files only when the license file used to import the vendor daemon contains the license file path as a relative path on its **VENDOR** line.
- Any existing demo vendor daemon and associated license files and log files are not imported. The installer always installs an up-to-date version of the demo vendor daemon and the files required to run it.

Upgrading OpenSSL Libraries

To enable customers to quickly upgrade to a higher version of OpenSSL libraries, lmadmin is dynamically linked against the OpenSSL libraries.



Task

To upgrade to a higher version of OpenSSL libraries:

After installing lmadmin and before running lmadmin, add the OpenSSL dynamic libraries path to the environment variable `LD_LIBRARY_PATH` (or `DYLD_LIBRARY_PATH`, depending on the platform). In the default scenario of using the pre-packaged OpenSSL libraries, the lmadmin installation directory path (or **<platform>\lmadmin** directory), where the OpenSSL libraries are present, must be added to the environment variable `LD_LIBRARY_PATH/DYLD_LIBRARY_PATH`.

For example:

- For Linux, SunOS SPARC, SunOS x86 platforms, use the LD_LIBRARY_PATH environment variable:
`export LD_LIBRARY_PATH=$LD_LIBRARY_PATH:<OpenSSL dynamic libraries path>`



Note • On Solaris SPARC machines it might also be required to add the directory where `libgcc_s.so.1` library file is present, to the `LD_LIBRARY_PATH`. Usually the `libgcc_s.so.1` file is located in `/usr/sfw/lib/` on Solaris 11 and in `/usr/local/lib` on Solaris 9 machines.

- For OS X platforms, use the DYLD_LIBRARY_PATH environment variable:
`export DYLD_LIBRARY_PATH=$DYLD_LIBRARY_PATH:<OpenSSL dynamic libraries path>`

The `ladmin` provided for AIX platforms does not support OpenSSL decoupling. Therefore, the AIX `ladmin` is linked against the static libraries of OpenSSL.

Only the following type of OpenSSL upgrades are supported by Flexera Software:

- Upgrade from X.Y.Za to X.Y.Zb—Low risk (e.g. 1.0.2h to 1.0.2k version of OpenSSL)

More significant upgrades are unsupported due to possible API incompatibility issues; for example, an upgrade from 1.0.2 to 1.0.3 is unsupported.

Uninstalling ladmin

The `ladmin` uninstaller removes all data folders (**conf**, **cache**, **logs**, and **conf**) and all executables, DLLs and license files. When you execute the uninstaller, you can choose to save log files and the **server.xml** file.



Task

To uninstall ladmin:

1. In folder `<ladmin_install_dir>\uninstall` (on Windows, the default is **C:\Program Files (x86)\FlexNet Publisher License Server Manager\uninstall**), execute **Uninstall FlexNet Publisher License Server Manager** to start the uninstaller.
2. In the panel **Get User Input for saving log and server.xml files**, select the checkbox **Yes save the files** if you want to save log files and `server.xml` files. Click **Next**. If you selected to save log files, on the next panel, specify a path. Click **Next**.
3. In the panel **Get User Input**, select **Yes** if you want to stop and remove the service. Click **Next**.
4. Click **Uninstall**.

Using lmadmin

Specifying the “conf” Folder

In a default `lmadmin` installation on a Windows platform, the **conf** folder is installed in the runtime data directory under **ProgramData** (that is, not in the same location where **lmadmin.exe** is installed). Therefore, for all operations that involve updates to files located in the **conf** folder (for example, **server.xml**), you need to specify the location of **conf** using the `-configDir` command:

```
lmadmin.exe -configDir <conf_path>
```

where `<conf-path>` is the path to the **conf** folder (for example, `C:\ProgramData\FLEXlm\lmadmin\conf`).

For command-line examples listed within this chapter, it is assumed that the **conf** folder is not installed in the same location as **lmadmin.exe**.

In installations on non-Windows platforms, and in Windows installations where the **conf** folder is installed in the same location as **lmadmin.exe**, using the `-configDir` command is not required.

Manually Starting the License Server Manager

You can start the license server using one of the following methods:

- Windows platforms: If the **conf** folder has been installed in the same location as **lmadmin.exe**, open the installation directory in Windows Explorer and double-click the **lmadmin.exe** file. This mechanism does not allow you to specify non-default command-line arguments.
- Execute the `lmadmin` command from the root installation directory. To see a list of available command-line arguments, execute the command:

```
lmadmin -help
```

The help display identifies the default arguments and which arguments are *persistent*, options that will remain in effect for later instances of `lmadmin`.

- Create a shell script file (UNIX) or a batch file (Windows) that will run the `lmadmin` command with your desired command-line arguments and then execute that file. For a default installation on a Windows platform, specify the location of the **conf** folder.



Note • If either the default license server port or the HTTP port for the user interface is in use, the license server manager will not start. For instructions see [License Server Manager Not Starting](#).



Important • In addition, ensure that the `http/https` ports and the licensing ports (required by `lmadmin`) and the vendor daemon ports are opened on the firewall, so that remote clients can checkout licenses and the HTTP clients/browsers can connect to the `lmadmin` web GUI.

License Server Manager Not Starting

Incorrect Port

The license server manager will not start if either of the following ports are in use:

- Default license server port (no ports in range 27000 to 27009 available)
- Default HTTP port for the license server manager user interface (port 8090)



Task

To check for this error and correct it:

1. Run `ladmin` from the command line using the `-foreground` argument:

```
ladmin -configDir <conf_path> -foreground
```

2. Examine the output at the command prompt. The following shows typical output when there is a clash on the HTTP port:

```
<OS 10048>Only one usage of each socket address <protocol/network address/port> is normally
permitted. : make_sock: could not bind to address 0.0.0.0:8090 no listening sockets available,
shutting down
Unable to open logs
```

3. Reconfigure any port where there is a clash:

- Use the `-licPort` argument for the license server port.
- Use the `-webPort` argument for the HTTP port.

For example, the following command reconfigures the HTTP port to 8091:

```
ladmin -configDir <conf_path> -webPort 8091
```

When you have reconfigured the HTTP port, you access the license server management interface using the new port number. So for `ladmin -configDir <conf_path> -webPort 8091`, connect to the URL, `http://<server>:8091`.

Insufficient Privileges (Windows only)

If the `ladmin` service does not start due to an “Access denied” error, ensure that it has sufficient privileges.

The `ladmin` folders that are updated during run time should be installed under **ProgramData**, to allow the service, which has Local Service privileges, to modify these files.

Manually Stopping the License Server Manager

The `allowStopServer` command-line argument toggles the presence of the **Stop Server** button in the `ladmin` user interface. The default is the **Stop Server** button is present. Click the **Stop Server** button in the Administration section of the license server management interface to shut down the license server manager (`ladmin`) and all vendor daemons.

If `ladmin` is started with the command-line argument `-allowStopServer no`, or if `-allowStopServer no` was the most recent use of the `-allowStopServer` argument, you cannot stop the license server using the license server management interface. In this situation, to stop the license server you must stop the `ladmin` process.

On UNIX systems, you can use the `ps` utility to identify the process and the `kill` command to terminate it.



Caution • Do not use `kill -9`, use only `kill` with its default signal; otherwise, the license server will not shut down cleanly.

On Windows systems, you can use the Task Manager to identify the **ladmin.exe** process and stop it.

You cannot restart the license server from the management interface. You must restart the license server as described in the previous section.

Accessing the License Server Management Interface

The license server management interface has two modes of operation—Standard mode and Section 508 mode. Either mode is accessible from a supported Web browser. See [System Requirements for ladmin](#) for a list of supported Web browsers.

1. Make sure that you have started the license server.
 2. Open the Web browser and browse to one of the following URLs:
- **Standard mode**—This is the standard license server management interface:

`http://<server>:8090`

where `<server>` is the system name where the license server is running.

- **Section 508 mode**—Section 508 mode provides access to people with disabilities and has the same capabilities that are available in Standard mode:

`http://<server>:8090/login508`

where `<server>` is the system name where the license server is running. (The term “Section 508 mode” comes from Section 508, 36 CFR 1194.21, “Requirements for Software Applications and Operating Systems” of the 1998 amendment to the Federal Rehabilitation Act.)

Signing in to ladmin as an Administrator

To use the following pages of the license server management interface, you must sign in as an administrator:

- System Information
- User Configuration
- Alert Configuration
- Server Configuration
- Vendor Daemon Configuration

When `ladmin` is first installed, the administrator user name and password are both set to **admin**. Use this information when you first sign in to the interface as an administrator.



Note • If `ladmin` is running on a Windows machine, you can also sign in to the interface using the Active Directory user ID specified as an `ladmin Administrator` (either directly or via the specified Active Directory group) during

ladmin installation. However, this type of sign-in is available only if your *ladmin* installation prompted for an Active Directory domain user or group name and if this information was provided.

Viewing the ladmin Log Files

Application log files (except the **report.log** file) are written to the **<ladmin_install_dir>/logs** directory (non-Windows platforms) or **<ladmin_runtimedata_dir>\logs** (default installations on Windows platforms).

Table 9-3 • Log files

Log File Name	Description
access.log	Contains information recorded about access to the license server management interface.
ladmin.log	Contains information recorded by the license server.
web.log	Contains information recorded by the license server management interface. This file does not contain information about login events. See the access.log file for that information.
<vendor>.log	These files contain information recorded by the corresponding vendor daemons (where <i><vendor></i> is the vendor daemon name). Each vendor daemon has its own log file, called the debug log file. In the installation package, you should see the demo.log file as the debug log file for the default demo vendor daemon.
report.log	A sample report log for the demo vendor daemon. Each vendor daemon can maintain a separate report log to record information about features that have been checked out by users. By default, a vendor daemon does not maintain report logs. This capability (in addition to the location of the report log file) must be enabled using the Options file.
FLEXnet_Publisher_License_Server_Manager_Install_MM_dd_yyyy_hh_mm_ss.log	A log recording events of the <i>ladmin</i> installation. This file is usually created in the uninstall\Logs directory located under the installation root directory. However, the <i>ladmin</i> installer might create it under a different name and location. If necessary, contact the publisher for the log file’s name and location.

 **Note** • Prior to *ladmin* 11.10.1, the installation log file was created directly under the installation root directory.

Managing ladmin from the Command Line

This section describes some of the common tasks that can be performed using the *ladmin* command line and the command-line arguments.

Adding a Vendor Daemon to ladmin

The ladmin license server must be configured with data about vendor daemons and license files. To add a vendor daemon, you must import it using a license file. You can do this from the command line (or from the ladmin user interface.)



Note • FlexNet Publisher provides a sample vendor daemon (demo or demo.exe) that you can use with ladmin. To use this vendor daemon, first copy it and its associated library from the <platform> directory to the <platform>\ladmin\demo directory. (The associated library is one of the following: demo_libFNP.so for UNIX, demo_libFNP.dll for Windows, demo_server_libFNP_notr.so for AIX, or demo_libFNP.dylib for Mac.) Then, issuing the command described in the following procedure, import the vendor daemon, using the sample license file ladmin\demo\demo.lic.



Task **To add a vendor daemon from the command line:**

1. Create or locate a valid license file (for example, mylicense.lic) with the appropriate SERVER lines, VENDOR lines, and feature definition lines.
2. Make sure that the vendor daemon executable is in the correct location relative to ladmin. This location is defined in the VENDOR line.
3. Import the license file by executing the following command:

```
ladmin -configDir <conf_path> -import <mylicense.lic>
```

where <mylicense.lic> is the path and name of the license file, and <conf_path> is the path to the **conf** folder. This command imports the license file, but does not start the license server.

When you import a license file, the license server configuration file (Windows:

<ladmin_runtimedata_dir>\conf\server.xml; non-Windows: <ladmin_install_dir>/conf/server.xml) is populated with the vendor daemon information (vendor name, vendor daemon path, port number, etc.).

4. Start the license server. See [Manually Starting the License Server Manager](#).



Note • For information about how to import a license file using the license server management interface, see the Online help available from within the license server management interface.

Configuring the License File Upload Directory

The license file upload directory is the location where copies of license files used by ladmin are stored when license files are imported using the **Import License** button on the **Vendor Daemon Configuration** tab or the -import command-line argument.

When this location is not configured, the default settings create the following directory structure into which license files are uploaded:

```
..\ladmin_runtimedata_dir\licenses\<vendor daemon name>\
```

For example, on Windows when ladmin is installed in the default location and two vendor daemons, demo and publisherA, are being managed by ladmin, the following directories are created when license files for these vendor daemons are imported:

C:\ProgramData\FLEXlm\ladmin\licenses\demo

C:\ProgramData\FLEXlm\ladmin\licenses\publisherA

The license file that contains license rights for the vendor daemon demo is copied to the **..\demo** directory. The license file that contains license rights for the vendor daemon publisherA is copied to the **..\publisherA** directory. When additional license files are imported for either of these vendor daemons, they are uploaded to the appropriate vendor daemon-specific directory.

You can replace this default configuration as described in the following instructions. Typically the license file upload directory is configured when ladmin is installed for the first time and then not altered. This ensures that license files, once imported, are available to ladmin and the vendor daemons it manages.



Task

To configure the license file upload directory:

1. If ladmin is running, shut it down ([Manually Stopping the License Server Manager](#)).
2. From the command line, execute an ladmin command using the -uploadDir argument.

The upload directory can be specified either as a relative or absolute path. When a relative path is used, it is relative to the current directory. Additionally a special string, %v, can be used to include the vendor daemon name in the directory path. Thus the following example specifies that the upload directory will be located at **C:\ProgramData\FLEXlm\ladmin\<vendor>\licenses**:

```
ladmin -configDir C:\ProgramData\FLEXlm\ladmin\conf -uploadDir
C:\ProgramData\FLEXlm\ladmin%\v\licenses
```

Configuring ladmin License Server Manager as a Windows Service with a Three-Server Configuration

Configure and maintain a set of three license server systems specifically for three-server redundancy. This provides fail over protection only. You manage only one version of the license file and vendor daemon on all three license servers. This configuration option is only available when licenses are held in license files. Using the three-server redundancy capability in FlexNet Publisher, all three license servers operate to form a triad.



Task

Procedure to run ladmin as a service on a three-server configuration:

1. Go to the **i86_n3\ladmin** directory and import the license file on each of the three servers, using the following command:


```
ladmin.exe -configDir <conf_path> -import <ThreeServerLicFile> [-force]
```
2. Install the service on each of the three servers, using the following command:


```
ladmin.exe -configDir <conf_path> -installService <Servicename>
```
3. From the **Services** window, start the installed service on each of the three servers. A quorum should get established.

Example

The three-server license file can have a format similar to the one shown below:

```

SERVER 172.18.24.193 00155d18e600 27000
SERVER 172.18.24.112 000c2954c827 27000
SERVER 172.18.24.184 000c29020077 27000
VENDOR demo demo/demo
USE_SERVER
FEATURE AgilentOpenLABSharedServices demo 1.0 01-feb-2020 1 \
ISSUED=01-feb-2020 SIGN="001D 1890 5872 AF29 11BB 274B 73B4 \
3700 D6F9 4DAD 435C AC50 5AE5 78A8 CFE5"
FEATURE TestFeature1 demo 1.0 30-sep-2020 1 ISSUED=01-feb-2020 \
SIGN="001B ED1F 6F7A 4DF0 1E92 4ECF DFBD 5100 639A 0896 E6FF \
6AE8 ACA0 B57F F670"
FEATURE TestFeature2 demo 1.0 30-sep-2020 3 ISSUED=01-feb-2020 \
SIGN="0032 404D ED9E 69AE 2EED 6E3A E091 E300 90E5 6F1B 405A \
6765 F4E1 8E34 A6D8"

```

Accessing lmadmin License Server Manager as a Windows Service with a Three-Server Configuration

The license server management interface has two modes of operation—Standard mode and Section 508 mode. Either mode is accessible from a supported Web browser. See [System Requirements for lmadmin](#) for a list of supported Web browsers.

1. Make sure that you have started the license server.
2. Open the Web browser and browse to one of the following URLs:
 - **Standard mode**—This is the standard license server management interface:

```
http://<Master node>:8090
```

where *<master node>* is the IP address or host name of the current master node.

- **Section 508 mode**—Section 508 mode provides access to people with disabilities and has the same capabilities that are available in Standard mode:


```
http://<Master node>:8090/login508
```

where *<Master node>* is the IP address or host name of the current master node.

For more information on Three-Server Redundancy, refer to the section [Overview of Three-Server Redundancy](#) on page 178.

Below is a sample output of the lmadmin GUI for Three-Server Redundancy:

Figure 9-1: lmadmin Three-Server Redundancy



http://[fec0::1:20f:feff:fed3:9373]:9009/systeminfo?vendor=qavend8&licenseTab=floating&selected=
 ew Favorites Tools Help
 FlexNet Administrator

FlexNet Publisher

System Information

- Release Version: 11.11.0
- License Server Manager Port in Use: 29009
- Display: BLR-P7106943
- Host Name: BLR-P7106943
- Host Domain Name: BLR-P7106943.NESSINBLR.COM
- IPv4 Address: 172.18.25.194
- IPv6 Address: fec0:0:0:1:20f:feff:fed3:9373
- Ethernet Address: 000ffed39373
- Volume Serial Number: 1c03c533
- Local Stop Server Allowed: Yes
- Remote Stop Server Allowed: Yes
- License Reclaim Allowed: No

Three Server Redundancy Group Information

- Quorum State: Up
- Master: fec0:0:0:1:20f:feff:fed3:9373
- Heartbeat Interval: 0
- Primary Is Master: false

Group Member Host	Port	Status
fec0::1:20f:feff:fed3:9373	29009	Active
fec0::1:2e27:d7ff:fe3b:e2d8	29009	Active
fec0::1:ca2a:14ff:fe55:90de	29009	Active

System Information
 User Configuration
 Alert Configuration
 Server Configuration
 Vendor Daemon Configuration

Installing ladmin License Server Manager as an Operating System Service

While it is possible to manually start and stop the ladmin license server manager, it is recommended that you install it as a service on the operating system so that it will automatically start whenever the operating system restarts.



Important • For security reasons, Flexera Software recommends that the license server be run with non-elevated user privileges (which, in turn, the vendor daemon inherits). See the later section, [Running FlexNet Publisher License Server as a System Service With Non-Elevated Privileges](#), for details on enabling the ladmin operating-system service to run under a non-Root or non-administrator user account.

Windows Systems

As part of the ladmin installation process on Windows systems, the ladmin installer might provide the option to configure the ladmin license server manager as a system service. However, only users in the Windows Administrators group can successfully perform this action. The **Startup Type** is set to **Automatic** so that the service starts automatically when the system is restarted.

As an alternative, use the following ladmin command-line arguments to install and uninstall the service (see [Table 9-4](#)).



Important • After you execute the command to install the license server manager as a Windows service, the service is not started automatically. You must manually start the service for the first time using the Windows Services Console.

Table 9-4 • ladmin command-line arguments to configure ladmin as a Windows service.

ladmin Command-Line Argument	Description
-installService <i>service name</i>	Creates a Windows service (with the name you provide) to run the license server manager. The service will run under the <i>LocalService</i> account.
-removeService	Uninstalls the Windows service with the name you specified. Make sure you stop the service before removing it.
-delay <i>nn</i>	Sets the number of seconds (<i>nn</i>) to delay between the time you start the service and the time it actually begins running. This delay is helpful when a FlexNet ID dongle is used to lock the license server to a machine (that is, when the FLEXid is used on the SERVER line). The license server can sometimes fail to start when a system reboots because the license server loads before the dongle device driver has a chance to load properly.

 **Note** • Use this option with the `-installService` argument.

Table 9-4 • ladmin command-line arguments to configure ladmin as a Windows service.

ladmin Command-Line Argument	Description
-giveaccess <service name>	Enables access to the installed FlexNet Licensing Service. This option adds the name of the ladmin service to the Discretionary Access Control List (DACL) of the FlexNet Licensing Service. This grants the ladmin service the permissions it requires to communicate with the FlexNet Licensing Service. This is required for the ladmin service to serve Trusted Storage features. Ensure that the FlexNet Licensing Service is installed beforehand.
<div style="text-align: center;"></div> <p>Note • Use this option as a separate argument, do not combine with any other options. For example: <code>ladmin.exe -giveaccess "FlexNet Licensing Service"</code>.</p>	

To run ladmin with any of the command-line arguments used to configure ladmin as a Windows service requires that the user has administrator privilege. (Windows versions enforce administrator privileges for installation or removal of a service.) Therefore, to use these arguments you must do the following:

- Sign in as an administrator before running ladmin with these arguments.
- Start the command prompt using the option **Run as Administrator**.

Linux Systems

On supported LSB platforms, the <ladmin_install_dir>/examples/service directory contains a shell-script file, ladmin. (Do not confuse this ladmin file with the executable for the license server manager.) This script file contains service installation instructions, including details on where this file should be installed on Red Hat Linux.

Additionally, see [Running FlexNet Publisher License Server as a System Service With Non-Elevated Privileges](#) for instructions on modifying the script to run the ladmin system service with non-elevated privileges.



Note • The instructions in the sample script might work on other ladmin-supported UNIX platforms with minor changes.

OS X Systems

On OS X Systems, administrators have to create their own startup script in a directory such as /Library/StartupItems/ladmin. The installed <ladmin_install_dir>/examples/service script is the same script as installed for Linux and Solaris systems and is provided *for reference only*; it will not work properly on OS X systems. For more information on installing an executable file as a system service (and running it with non-elevated privileges) on OS X systems, see any of the many publicly available references such as <http://www.oreilly.com/pub/a/mac/2003/10/21/startup.html>.



Note • Flexera Software is not responsible for the accuracy of information obtained from such reference sources or for the results of the startup script that you write.

Running FlexNet Publisher License Server as a System Service With Non-Elevated Privileges

Flexera Software recommends that the `lmadmin` license server manager be run with non-elevated user privileges. (The vendor daemon inherits these same privileges.) This practice ensures that any security vulnerabilities exploited by malicious users with access to the corporate network will have minimal impact beyond the licensing services.

The instructions below are examples for enabling the `lmadmin` operating-system service to run under a non-root or non-administrator user account. The instructions assume that you have `lmadmin` already installed.

Procedure Overview

Managing the license server as a system service typically requires three main phases:

- **Phase 1**—Install the license server as a system service. This step typically requires elevated privileges. See the previous section, [Installing lmadmin License Server Manager as an Operating System Service](#).
- **Phase 2**—Identify or create a user account with non-elevated privileges. You should create a user account (either a domain account or a local account) that is dedicated to running the license server system service. In the instructions that follow, this user account is referred to as the *Service User account*. Make sure that this Service User account has sufficient permissions to read the license files and write the log files in the designated folders.
- **Phase 3**—Configure the installed license server system service to use the Service User account. This step requires elevated privileges as well.

The following sections provide steps (based on the above procedure overview) for enabling the `lmadmin` license server to run with non-elevated user privileges on various operating-system platforms. Adjust these steps as needed for your specific platform or platform version.

Windows Systems

Use the following procedure to run the `lmadmin` system service with non-elevated privileges on Windows.



Task

To configure the `lmadmin` system service to run with non-elevated user privileges:

1. If `lmadmin` was *not* set up as a Windows service during the `lmadmin` installation process, install the service from the command line:

```
lmadmin configDir <conf_path> -installService <servicename>
```

where *servicename* is the name of the `lmadmin` Windows service.

This step requires elevated user privileges.

2. Create a Service User account either on the local system or on the domain.
3. Grant this lesser-privileged account the permissions to start and stop the service. Use any appropriate method, such as Security Descriptor Definition Language or a publicly available third-party tool such as SetACL.

The following steps use SetACL to manage the permissions for the service:

- a. Download and install the command-line SetACL utility.

6. Save the changes in the script.
7. To start the ladmin system service under the user you specified for ladminUser, execute the following command:

```
service ladmin start
```

Other UNIX Systems

After configuring ladmin to start up as a system service, as described in [Installing ladmin License Server Manager as an Operating System Service](#), modify the startup script (ladmin or similar shell script) to run the ladmin service with non-elevated privileges. Use the instructions in the previous section, [Linux Systems](#), as a guide for editing the script. However, adjust the procedure as needed for your specific UNIX platform.

OS X Systems

See the previous section, [OS X Systems](#), under [Installing ladmin License Server Manager as an Operating System Service](#).

ladmin Command-line Arguments

This section describes in outline each of the ladmin command-line arguments. Arguments defined as persistent will remain set until they are reset.

Usage

```
ladmin [-version] [-config <configFile>] [-configDir <configFileDirectory>] [-cacheDir
<cacheDirectory>][-root <ladmin_install_dir>] [-force] [-giveaccess <service name>] [-import
<licenseFileList>]
[-importInstallation <oldInstallDirectory>][-config <configFileForImport>][-configDir
<configDirForImport>]] [-licPort <licenseServerPort>][-webPort <httpPort>]
[-allowStopServer <yes|no>] [-allowRemoteStopServer <yes|no>][-allowLicenseReclaim <yes|no>]
[-installService <servicename>] [-delay <seconds>] [-removeService <serviceName>]
[-defaultAdminUser <domain\username>] [-defaultAdminGroup <domain\groupname>]
[-uploadDir <uploadDirectory>] [-useradd <userid> -Pass <password> -Role <roleType> [-FirstName <name>]
[-LastName <name>]] [-usermod <userid> [-Pass <password>] [-Role <role_type>] [-FirstName <name>] [-
LastName <name>]] [-userdel <userid>] [-foreground] [-adminOnly <yes|no>] [-logDir <logDirectory>]
```

Table 9-5 • lmadmin Command-line Arguments

Argument Syntax	Description	Function
-adminOnly <yes no>	Default—Yes Persistent—Yes Set from UI—No	<p>Restricts usage of lmdown, lmreread, and lmremove—as well as lmswitch, lmswitchr, and lmnewlog. If you set -adminOnly no, command-line access to these utilities is unrestricted. (Access to related features in the lmadmin UI is governed separately by lmadmin login credentials.)</p> <p>By default, lmadmin restricts command-line access to these utilities. The default argument, -adminOnly yes, overrides other lmadmin command-line options, such as -allowLicenseReclaim, -allowStopServer, and -allowRemoteStopServer.</p> <p>Restrictions vary depending on the operating system on which lmadmin is running.</p> <p>On Windows, command-line access to these utilities is completely restricted. If -adminOnly yes is used when starting lmadmin, no user on Windows can shut down the license server with lmdown, nor can they use the lmswitch, lmswitchr, and lmnewlog command-line utilities.</p> <p>On UNIX, -adminOnly yes permits access by the root user only, by default. However, if you define a UNIX group called lmadmin, then access is permitted to members of that group only. (If root is not a member of this group, then root does not have permission to use any of the above utilities.)</p>
-allowLicenseReclaim <yes no>	Default—No Persistent—Yes Set from UI—No	<p>Controls the operation of lmremove (in License File-Based Licensing). If set to yes, licenses can be reclaimed from a user. If set to no, licenses cannot be reclaimed from a user.</p>



Note • Restrictions from the -adminOnly yes argument may prevent license reclamation even if you set -allowLicenseReclaim yes.

Table 9-5 • ladmin Command-line Arguments

Argument Syntax	Description	Function
-allowStopServer <yes no>	Default—Yes value Persistent—Yes Set from UI—No	<p>Configures how the license server can be stopped.</p> <p>If set to yes, local clients can stop the license server using either lmdown or the Stop Server button in the UI.</p> <hr/> <p> Note • <i>Restrictions from the -adminOnly yes argument may prohibit stopping the server from the command line even if you set -allowStopServer yes.</i></p> <p>If set to no, then the license server must be stopped by stopping the process. See Manually Stopping the License Server Manager.</p> <hr/> <p> Note • <i>Setting -allowStopServer no also sets -allowRemoteStopServer to no.</i></p>
-allowRemoteStopServer <yes no>	Default—No value Persistent—Yes Set from UI—No	<p>Configures whether the license server can be stopped from a remote location.</p> <p>If set to yes, then you can stop the license server from a remote location and local clients can stop the license server using either lmdown or the Stop Server button in the UI.</p> <hr/> <p> Note • <i>Restrictions from the -adminOnly yes argument may prohibit remotely stopping the server from the command line even if you set -allowRemoteStopServer yes.</i></p> <p>If set to no, then it must be stopped from a local client. See Online help for further details.</p> <hr/> <p> Note • <i>Setting -allowRemoteStopServer yes when -allowStopServer is not defined, forces -allowStopServer to be set to yes.</i></p>

Table 9-5 • lmadmin Command-line Arguments

Argument Syntax	Description	Function
-config <configFile>	Default—server.xml Persistent—Yes Set from UI—No	Defines the name of the license server configuration file to use when starting the license server manager. If all defaults are set, the path and name is the following: <lmadmin_runtimedata_dir>\conf\server.xml.
-configDir <configDir>	Default— <lmadmin_runtimedata_dir> \conf (Windows); <lmadmin_install_dir>/conf (non-Windows) Persistent—Yes Set from UI—No	Defines the directory where the license server configuration files are located.
-cacheDir <cacheDirectory>	Default— <lmadmin_runtimedata_dir> \cache (Windows); <lmadmin_install_dir>/cache (non-Windows) Persistent—Yes Set from UI—No	Defines the destination directory path for cache files.
-delay <seconds>	Default—0 Persistent—Yes Set from UI—No	Used when configuring the license server as a service on Windows. See Installing lmadmin License Server Manager as an Operating System Service .

Table 9-5 • ladmin Command-line Arguments

Argument Syntax	Description	Function
-defaultAdminUser <domain\username>	Default—N/A Persistent—Yes Set from UI—Yes	<p>Adds the specified Windows Active Directory user as an ladmin Administrator. The license administrator can then log in to the ladmin user interface initially using this user ID (and its Active Directory password) and proceed to perform administrative tasks.</p> <p>To identify this user, use the format <i>domain\username</i>, where <i>domain</i> is a valid Windows Active Directory domain to which the machine running ladmin has a trusted relationship, and <i>username</i> identifies a valid account within that domain. This value is not case-sensitive and can include up to 64 characters.</p> <p> Note • Use this argument sparingly. Its main purpose is to provide initial access to the ladmin interface.</p>

Table 9-5 • ladmin Command-line Arguments

Argument Syntax	Description	Function
-defaultAdminGroup <domain\groupname>	Default—N/A Persistent—Yes Set from UI—Yes	<p>Adds the specified Windows Active Directory group as an ladmin Administrator. The license administrator can then log in to the ladmin user interface initially using any Active Directory user ID (and its associated password) belonging to this group and proceed to perform administrative tasks.</p> <p>To identify this group, use the format <i>domain\groupname</i>, where <i>domain</i> is a valid Windows Active Directory domain to which the machine running ladmin has a trusted relationship, and <i>groupname</i> identifies a valid account within that domain. This value is not case-sensitive and can include up to 64 characters.</p>



Note • Consider the following:

- *Setting a domain group as the ladmin Administrator is helpful in a large enterprise where you might have several license administrators who need access to the interface. For more information, see the Online help once you have opened the interface.*
- *Use this argument sparingly. Its main purpose is to provide initial access to the ladmin interface.*

Table 9-5 • lmadmin Command-line Arguments

Argument Syntax	Description	Function
-force	Default—Do not overwrite settings Persistent—No Set from UI—No	Use with the -import argument to overwrite existing vendor daemon settings in the license server configuration file. The following settings are overwritten or reset to the default: <ul style="list-style-type: none"> • License file location (overwritten). • Vendor daemon location (overwritten). • Vendor daemon port (reset to default). • Restart retries (reset to default). • Date-based versions (reset to default). • Overwrite vendor daemon log (reset to default). • Vendor daemon log location and name (reset to default).
-foreground	Default—Run in background Persistent—No Set from UI—N/A	Runs lmadmin in the foreground (output status and errors are sent to the command window).
-giveaccess <service name>	Default—N/A Persistent—No Set from UI—N/A	Enables access to the installed FlexNet Licensing Service. This option adds the name of the lmadmin service to the Discretionary Access Control List (DACL) of the FlexNet Licensing Service. This grants the lmadmin service the permissions it requires to communicate with the FlexNet Licensing Service. This is required for the lmadmin service to serve Trusted Storage features. Ensure that the FlexNet Licensing Service is installed beforehand.

 **Note** • Use this option as a separate argument, do not combine with any other options. For example: `lmadmin.exe -giveaccess "FLexNet Licensing Service"`.

Table 9-5 • ladmin Command-line Arguments

Argument Syntax	Description	Function
-import <licenseFileList>	Default—N/A Persistent—N/A Set from UI— Import License button	Updates the license server configuration file with information extracted from the specified license files. See license_file_list for details of the format of <licenseFileList>. This option does not start ladmin. The only arguments that can be combined with -import are: -config, -configDir, -cacheDir, and -force.
-importInstallation <oldInstallDirectory> [-config <configFileForImport>] [-configDir <configDirForImport>]	Default—N/A Persistent—N/A Set from installer—Specify in Import Files from Previous Installation in the ladmin installer.	Imports configuration information from the specified existing ladmin installation directory or from a specified location for the license server configuration files (optional use of -config or -configDir). This option does not start ladmin. The only arguments that can be combined with -importInstallation are: -config, -configDir, and -root.
-installService <serviceName>	Default—Do not install ladmin as a Windows service Persistent—N/A Set from UI—No	Used when configuring the license server as a service on Windows. See Installing ladmin License Server Manager as an Operating System Service .
-licPort <licenseServerPort>	Default—First available in range 27000-27009 Persistent—Yes Set from UI—Specify for License Server Manager Port (located under the License Server Configuration heading on the Server Configuration tab on the Administration page)	Configures the license server manager port. To set a specific port, enter a positive integer for <licenseServerPort>. A valid number is any unused port number in the range 0 to 65535. On UNIX, choose a port >1024, since those <1024 are privileged port numbers. If not specified, the license server will automatically use the next available port number in the range 27000 to 27009. Applications, when connecting to a server, try all numbers in the range 27000 to 27009.



Note • For security purposes, best practice is not to use a default port for the license server. Instead, specify a port number outside of the range 27000 to 27009.

Table 9-5 • lmadmin Command-line Arguments

Argument Syntax	Description	Function
-logDir <logDirectory>	Default— <lmadmin_runtimedata_dir> \logs (Windows); <lmadmin_install_dir>/logs (non-Windows) Persistent—Yes Set from UI—No	Writes the lmadmin logs to the location you specify for <logDirectory>. Enter an absolute path for <logDirectory>. Assuming no vendor daemon logs have been set (in the options file) to write to a custom location, lmadmin writes all lmadmin logs to the location you set for <logDirectory>. When a custom vendor daemon log location is set, that setting overrides the -logDir setting for that particular vendor-daemon log.
-removeService <serviceName>	Default—N/A Persistent—N/A Set from UI—No	Used when configuring the license server as a service on Windows. See Installing lmadmin License Server Manager as an Operating System Service .
-root <lmadmin_install_dir>	Default— root installation directory. Persistent—No Set from UI—No	Specifies the root directory for lmadmin. This enables you to issue an lmadmin command from somewhere other than the directory where lmadmin is installed.
		 Note • Any command-line arguments that specify relative paths define paths relative to the current directory and not the directory specified with -root.
-uploadDir <uploadDirectory>	Default— <lmadmin_runtimedata_dir> \licenses\ <vendor> (Windows); <lmadmin_install_dir>/ licenses/<vendor> (non- Windows) Persistent—Yes Set from UI—No	Configures the directory where license files that are uploaded to the license server manager are stored. A directory with the name of the vendor daemon can be set by using the string “%v” as in the following example: -uploadDir flexlicenses%v

Table 9-5 • ladmin Command-line Arguments

Argument Syntax	Description	Function
-useradd <userid> -Pass <password> -Role <roleType> [-FirstName <name>] [-LastName <name>]	Persistent—Yes Set from UI—Yes	<p>Adds a new ladmin user-interface user. Provide the following parameters:</p> <ul style="list-style-type: none"> • -useradd <userid>—Provide either value: <ul style="list-style-type: none"> For a locally managed account (that is, defined and managed by ladmin), a user-defined sign-in ID, up to 64 characters. The value is case-sensitive and can include spaces but no backslashes (\). or For a Windows Active Directory domain account, the account ID in the following format: <p><domain>\<username> <groupname></p> <p>where <domain> is the active Active Directory domain to which the machine running ladmin has a trusted relationship and <username> or <groupname> identifies a valid user or group account existing within that domain. This value is not case-sensitive and can include up to 64 characters. Separate multiple domains with a backslash (\).</p>
		<p> Note • When a Windows Active Directory group account is defined to ladmin, only the group name is identified in the account. However, a user must sign in to ladmin using a domain user name (not the group name) and its password. ladmin then contacts the domain server to validate the user as a member of a group account defined to ladmin.</p> <ul style="list-style-type: none"> • -Pass <password>—(Locally managed accounts only) Specify the password for the specified user ID, up to 32 characters.

Table 9-5 • ladmin Command-line Arguments

Argument Syntax	Description	Function
<pre>-useradd <userid> -Pass <password> -Role <roleType> [-FirstName <name>] [- LastName <name>]</pre> <p>(continued)</p>		<ul style="list-style-type: none"> ● -Role <roleType>—Specify one of these roles to assign ladmin user-interface privileges to the account: <ul style="list-style-type: none"> user—The user is limited to ladmin Dashboard functionality only.* Assign this role only when you are password-protecting the Dashboard.*** Otherwise, the user has automatic access to the Dashboard. admin—The user (locally managed or in Windows Active Directory) has administrator rights.** userGroup—(Windows Active Directory group account only) The domain group is limited to ladmin Dashboard functionality only.* Assign this role only when you are password-protecting the Dashboard.*** Otherwise, the group has automatic access to the Dashboard. adminGroup—(Windows Active Directory group account only) The domain group has administrator rights.** ● -FirstName <name>— (Locally managed accounts only; optional) The user’s first name. ● -LastName <name>—(Locally managed accounts only; optional) The user’s last name.
<pre>-usermod <userid> [-Pass <password>] [-Role <role_type>] [-FirstName <name>] [-LastName <name>]</pre>	<p>Persistent—Yes</p> <p>Set from UI—Yes</p>	<p>Allows you to modify the ladmin user-interface user account identified by the account ID (<userid>). You can modify the account’s role and, for locally managed accounts, the password and first and last names of the user. See the -useradd argument described previously in this table for descriptions of these parameters.</p>
<pre>-userdel <userid></pre>	<p>Persistent—Yes</p> <p>Set from UI—Yes</p>	<p>Removes the ladmin user-interface user account identified by the account ID (<userid>).</p>

Table 9-5 • ladmin Command-line Arguments

Argument Syntax	Description	Function
-webPort <httpPort>	Default—8090 Persistent—Yes Set from UI—Specify for HTTP Port (located under the Web Server Configuration heading on the Server Configuration tab on the Administration page)	Configures the TCP/IP port that the Web server uses to listen for communication with clients connecting to the license server management interface. See License Server Manager Not Starting for an example of how to use this argument.
-webSecurePort <httpsPort>	Default—0 Persistent—Yes Set from UI—Specify for HTTPS Port (located under the Secure Web Server Configuration heading on the Server Configuration tab on the Administration page)	Configures the TCP/IP port (five characters maximum) that the ladmin web server uses to listen for HTTPS (HTTP-over-SSL) communication. If you change the port, you must stop and restart the license server.  Important • Specify the -webSecurePort option only if you are configuring HTTPS communication with the ladmin web server interface.
-version	N/A	Outputs details of the ladmin version to the command prompt.

* Dashboard privileges provide access to all the ladmin user-interface Dashboard functionality. This includes viewing license activity and alerts, changing the user password (locally managed accounts only), and selecting a locale when multiple locales are configured on the system.

** Administrator privileges include all Dashboard privileges plus the ability to access the Administration page of the ladmin user interface. From this page, the administrator can perform license-server configuration and management tasks, and set up, edit, or delete other ladmin user accounts.

*** To password-protect the Dashboard, use the **Password Protect Dashboard** option on the Server Configuration tab located on the Administration page in the ladmin user interface.

Obtaining ladmin Command-Line Help

For a handy reference to ladmin command-line arguments, use this procedure.



Task *To obtain a handy reference of ladmin command-line arguments:*

1. Open a command-prompt window.
2. Change to the directory where the **ladmin** file is located.
3. Enter the following command to view a list of available arguments with a description of each:

```
ladmin -help
```

The help descriptions identify the default arguments and which arguments are *persistent*, arguments that will remain in effect for later instances of ladmin.

Extending ladmin License Server Capability

ladmin can be customized. These customizations require some programming. The ladmin installation package includes some example applications and files that demonstrate simple customizations.

Using the ladmin Web Service Interface

ladmin provides a Web service interface that exposes certain APIs that can be called from a custom-built utility. These services enable you to extend the core license server capabilities. The WSDL file needed to generate the client proxy can be found in the `<ladmin_install_dir>\wsdl` directory.

The ladmin installation package includes a set of examples in the `<ladmin_install_dir>\examples` directory that demonstrate how to implement certain capabilities using the Web service interface.

Creating an ladmin Alerter Service

The ladmin license server installation includes an example of how to implement an email alerter service. This service will poll for alerts and then send a user an email when an alert has been triggered.

Using the Alerter Service Email Alerts

The sample Alerter service utility runs on the license server and enables a user to receive alert notifications by email. To use the Alerter service, Java Runtime Environment (JRE) 1.6 or later (for OS X: JRE 1.7 or later) must be installed on the license server.

To start the Alerter service, there are two files in the `<ladmin_install_dir>\examples\alerter` directory:

- For Windows systems, the **runalerter.bat** file.
- For UNIX systems, the **runalerter** file.

When starting this service, you must configure certain command-line arguments to define the mail server, sender, receiver, and so on. To see the list of available command-line arguments for the runalerter script, type the following command:

```
runalerter -help
```

The source code for this utility is in the `<ladmin_install_dir>\examples\alerter\src` directory.

10

License Server Manager “Imgrd”

The *license server manager* is one of the components that make up a license server (the other being the vendor daemon). It handles the initial contact with FlexEnabled applications, passing the connection on to the appropriate vendor daemon. The purposes of the license server manager are to:

- Start and maintain all the vendor daemons listed in the VENDOR lines of the license file used to start `lmgrd`.
- Refer application checkout (or other) requests to the correct vendor daemon.

`lmgrd` is an application-based version of the license server manager. On most platforms it is controlled from a command-line. On Windows, `lmtools` can be used to manage `lmgrd`.

A newer `lmgrd` can be used with an older vendor daemon or FlexEnabled application, but a newer vendor daemon or FlexEnabled application might not work properly with an older `lmgrd`. Always use the latest version of `lmgrd`, which is available from the download site. See [Version Compatibility Between Components](#) for detailed information.

Ensure that the local host name resolution (in `/etc/hosts`) is handled before the following scenarios:

- To have regular heartbeat interval when you communicate between `lmgrd` and vendor daemon, and
- To successfully start the license server.

Imgrd Command-Line Syntax

When you invoke `lmgrd`, it looks for a license file that contains information about vendors and features.

Usage

```
lmgrd [-c license_file_list] [-l [+]debug_log_path]  
      [-2 -p] [-local] [-x lmdown] [-x lmremove] [-z] [-v] [-help]
```

The following table describes the syntax elements:

Table 10-1 • lmgrd Command-Line Syntax

Term	Description
-c <i>license_file_List</i>	Uses the specified license files.
-l [+] <i>debug_Log_path</i>	Writes debugging information to file <i>debug_Log_path</i> . This option uses the letter <i>l</i> , not the numeral 1. Prepending <i>debug_Log_path</i> with the + character appends logging entries. Use the -l option before other options to log all debugging information to <i>debug_Log_path</i> . See Debug Log File for more information on this file.
	 <p>Note • On Windows, it is best practice to set the location of <i>debug_Log_path</i> to a <i>ProgramData</i> sub-folder, since this location has user-write permission by default, which is needed when the license server runs as a service with <i>LocalService</i> permission.</p>
-2 -p	<p>On UNIX systems, -2 -p restricts usage of <i>lmdown</i>, <i>lmreread</i>, and <i>lmremove</i>—as well as <i>lmswitch</i>, <i>lmswitchr</i>, and <i>lmnewlog</i>—to a license administrator who is by default root. If there is a UNIX group called <i>ladmin</i>, then use is restricted to only members of that group. If root is not a member of this group, then root does not have permission to use any of the above utilities.</p> <p>On Windows systems, if <i>lmgrd</i> is started with -2 -p -local, <i>lmgrd</i> and the vendor daemon can only interact with the command-line utilities (<i>lmreread</i>, <i>lmnewlog</i>, <i>lmdown</i>, <i>lmremove</i>, and <i>lmswitch</i>) if these are located on the same machine and if they are run with <i>LOCALSYSTEM</i> privileges. -2 -p is effective, and supported, only when used together with -local.</p>
-local	<p>On UNIX systems, restricts the <i>lmdown</i> and <i>lmreread</i> commands to be run only from the same system where <i>lmgrd</i> is running. In the case of a three server setup, -2 -p -local can shut down any of the nodes in a triad server. As <i>lmdown</i> request from any of the node in the triad is considered as -local.</p> <p>On Windows systems, if <i>lmgrd</i> is started with -2 -p -local, <i>lmgrd</i> and the vendor daemon can only interact with the command-line utilities (<i>lmreread</i>, <i>lmnewlog</i>, <i>lmdown</i>, <i>lmremove</i>, and <i>lmswitch</i>) if these are located on the same machine and if they are run with <i>LOCALSYSTEM</i> privileges.</p>
-x lmdown	<p>Disables the <i>lmdown</i> command (no user can run <i>lmdown</i>). If <i>lmdown</i> is disabled, stop <i>lmgrd</i> using <code>kill pid</code> (UNIX), or stop the <i>lmgrd</i> and vendor daemon processes through the Windows Task Manager or Windows service.</p> <p>On UNIX, be sure the <code>kill</code> command does not have a -9 argument.</p>
-x lmremove	Disables the <i>lmremove</i> command (no user can run <i>lmremove</i>).
-z	<p>Runs in foreground. The default behavior is to run in the background.</p> <p>If -l debug_log_path is present, then no windows are used, but if no -l argument specified, separate windows are used for <i>lmgrd</i> and each vendor daemon.</p>

Table 10-1 • lmgrd Command-Line Syntax

Term	Description
-v	Displays the lmgrd version number and copyright and exits.
-help	Displays usage information and exits.
-reuseaddr	[optional] Allows the server to explicitly bind to a same port, which remains in TIME_WAIT state after the server restart or crash

 **Note** • It is recommended to use the `-reuseaddr` option only on non-Windows systems to avoid undefined behavior.



Note • The license search path can also be specified by setting the environment variable `LM_LICENSE_FILE` to the file's path name. The `-c` path specification will override the setting of `LM_LICENSE_FILE`.

Starting the License Server Manager on UNIX Platforms

If any licenses in the license file are counted (license count > 0), the license server manager, and hence the license server, must be started before the FlexEnabled application can be used.

The license server manager, `lmgrd`, is started either manually on the command line or automatically at system startup. Both methods are discussed in the following sections.



Note • Start `lmgrd` only on the system specified on the `SERVER` line in the license file.

If you are running license servers configured for three-server redundancy, maintain an identical copy of the license file (as well as the `lmgrd` and the vendor daemons binaries) locally on each system rather than on a file server. If you do not do this, you lose all the advantages of having redundant servers, as the file server holding these files becomes a single point of failure.



Important • In addition, ensure that the `http/https` ports and the licensing ports (required by `lmgrd`) and the vendor daemon ports are opened on the firewall, so that remote clients can checkout licenses and the HTTP clients/browsers can connect to the `lmgrd`.

Manual Start

Start `lmgrd` from the UNIX command line using the following syntax:

```
lmgrd -c license_file_list -L [+]debug_log_path
```

where

license_file_list is one or more of the following:

- the full path to a single license file
- a directory, where all files named *.lic in that directory are used

If the license_file_list value contains more than one license file or directory, they must be separated by colons on UNIX or semicolons on Windows.

debug_log_path is the full path to the debug log file.



Note • On Windows platforms, it is best practice to set the location of debug_log_path to a sub-folder of **ProgramData**. This location has user-write permissions by default, which are needed when the license server runs as a service with LocalService permission.

Prepending debug_log_path with the + character appends logging entries.

Start lmgrd by a user other than root since processes started by root can introduce security risks. If lmgrd must be started by the root user, use the su command to run lmgrd as a non-privileged user:

```
su username -c "lmgrd -c license_file_list -l debug_log_path"
```

where username is a non-privileged user. You must ensure that the vendor daemons listed in the license file have execute permissions for username. The paths to all the vendor daemons in the license file are listed on each VENDOR line.

Automatic Start

On UNIX, edit the appropriate boot script, which may be /etc/rc.boot, /etc/rc.local, /etc/rc2.d/Sxxx, /sbin/rc2.d/Sxxx. Include commands similar to the following. See the following notes for a full explanation.

```
/bin/su daniel -c 'echo starting lmgrd > \  
/home/flexlm/v11/hp700_u9/boot.log'
```

```
/bin/nohup /bin/su daniel -c 'umask 022; \  
/home/flexlm/v11/hp700_u9/lmgrd -c \  
/home/flexlm/v11/hp700_u9/license.dat >> \  
/home/flexlm/v11/hp700_u9/boot.log'
```

```
/bin/su daniel -c 'echo sleep 5 >> \  
/home/flexlm/v11/hp700_u9/boot.log'
```

```
/bin/sleep 5
```

```
/bin/su daniel -c 'echo lmdiag >> \  
/home/flexlm/v11/hp700_u9/boot.log'
```

```
/bin/su daniel -c '/home/flexlm/v11/hp700_u9/lmdiag -n -c\  
/home/flexlm/v11/hp700_u9/license.dat >> \  
/home/flexlm/v11/hp700_u9/boot.log'
```

```
/bin/su daniel -c 'echo exiting >>\n/home/flexlm/v11/hp700_u9/boot.log'
```

Please note the following about how this script was written:

- All paths are specified in full because no paths are assumed at boot time.
- Because no paths are assumed, the vendor daemon must be in the same directory as `lmgrd`, or the `VENDOR` lines in the license file must be edited to include the full path to the vendor daemon.
- The `su` command is used to run `lmgrd` as a non-root user, **daniel**. It is recommended that `lmgrd` not be run as root since it is a security risk to run any program as root that does not require root permissions. `lmgrd` does not require root permissions.
- **daniel** has a `cs` login, so all commands executed as **daniel** must be in `cs` syntax. All commands not executed as **daniel** must be in `/bin/sh` syntax since that is what is used by the boot scripts.
- The use of `nohup` and `sleep` are required on some operating systems, notably HP-UX. These are not needed on Solaris and some other operating systems, but are safe to use on all.
- `lmdiag` is used as a diagnostic tool to verify that the server is running and serving licenses.



Note • This does not start the vendor daemon until you reboot the system.

Starting the License Server Manager on Windows

This section provides procedural information on manual starts from the command line and how to configure the License Server Manager (`lmgrd`) as a service.

Manual Start from the Command Line



Task *To start `lmgrd` from the command line*

Start `lmgrd` as an application from a Windows command shell using the following syntax:

```
C:\fnp> lmgrd -c license_file_list -L [+]debug_log_path
```

where

- `license_file_list` is one or more of the following:
 - the full path to a single license file
 - a directory, where all files named `*.lic` in that directory are used
- `debug_log_path` is the full path to the debug log file

Prepending `debug_log_path` with the `+` character appends logging entries.

Spaces in pathnames require double quotes around the path.



Note • On Windows platforms, it is best practice to set the location of `debug_Log_path` to a sub-folder of **ProgramData**. This location has user-write permissions by default, which are needed when the license server runs as a service with `LocalService` permission.

The `lmgrd -a <Service Name>` command option adds the name of the `lmgrd` service to the Discretionary Access Control List (DACL) of the FlexNet Licensing Service. This grants the `lmgrd` service the permissions it requires to communicate with the FlexNet Licensing Service. This is required for the `lmgrd` service to serve Trusted Storage features. When you install `lmgrd` as a service, ensure that the FlexNet Licensing Service is installed beforehand.

Configuring the License Server Manager as a Windows Service

To configure a license server manager (`lmgrd`) as a service, you must have Administrator privileges. The service will run under the `LocalService` account. This type of account (`LocalService` account) is required to run this utility as a service.




Task

To configure a license server as a service:

1. Run the `lmtools` utility.
2. On the Service/License File tab, click the **Configuration using Services** option, and then click the **Config Services** tab.
3. In the **Service Name** field, type the name of the service that you want to define, for example, **DEMO License Manager**. If you leave this field blank, the service will be named FlexNet Publisher Service.
4. In the **Path to the lmgrd.exe file** field, enter or browse to **lmgrd.exe** for this license server.
5. In the **Path to the license file** field, enter or browse to the license file for this license server.
6. In the **Path to the debug log file** field, enter or browse to the debug log file that this license server writes. Prepending the debug log file name with the `+` character appends logging entries. The default location for the debug log file is the `c:\ProgramData\FNP_DIR\debug.log` folder. To specify a different location, make sure you specify a fully qualified path. It is best practice to set the location of `debug_log_path` to a subfolder of **ProgramData**. This location has user-write permission by default, which is needed when the license server runs as a service with `LocalService` permission.

7. To save the new **DEMO License Manager** service, click **Save Service**.

Figure 10-1: Completed Config Services Tab



Configuring the License Server Manager Service for a Delayed Start

In situations where the license server needs to wait for other drivers or services to start before it starts, you can configure a delay before the license server service starts. A typical scenario where a delay is needed is when a FlexNet ID dongle is used to lock the license server to a machine (the FLEXid is used on the SERVER line). In this scenario the license server will sometimes fail to start upon reboot of the system because the license server is loaded before the dongle device driver has loaded properly.



Task

To configure a delayed start for the license server manager service:

1. Configure the license server manager as a service ([Configuring the License Server Manager as a Windows Service](#)).
2. Locate the registry entry for your license server manager service at:
`HKEY_LOCAL_MACHINE\SOFTWARE\FLEXlm License Manager\service_name`
where `service_name` is the name of the license server manager service.
3. Optionally, to configure a delay longer than 20 seconds, add a string value to the registry entry and set the fields in this entry as follows:

Name - unlimitedServiceDelay

Type - REG_SZ (set automatically when a string value is created)

Data - no value set

4. Add a string value to the registry entry and set the fields in this entry as follows:

Name - serviceDelay

Type - REG_SZ (set automatically when a string value is created)

Data - the service delay in seconds. This value is limited to the range 1-20 seconds unless unlimitedServiceDelay has previously been defined (see Step 3).

Manually Starting the License Server Using the lmtools Utility

A graphical user interface to the license server manager tools is provided called lmtools. Some of the functions lmtools performs include:

- Starting, stopping, and configuring license servers
- Retrieving system information, including hostids
- Retrieving server status

In order to control the operation of lmgrd from the lmtools user interface, you first must configure it as a license server manager service. Follow the procedure in [Configuring the License Server Manager as a Windows Service](#) before proceeding.

Once the license server manager service is configured, lmgrd is started by starting the service from the lmtools interface.




Task *To start the service from the lmtools interface:*

1. Start lmtools and click the **Service/License File** tab.
2. Click the **Configuration using Services** option.

3. Select the service name from the list presented in the selection box. In this example, the service name is **DEMO License Manager**.

Figure 10-2: Service/License File Tab



4. Click the **Start/Stop/Reread** tab.
5. Start DEMO License Manager by clicking the **Start Server** button. DEMO License Manager license server starts and writes its debug log output to **C:\ProgramData\FNP_DIR\debuglog**.



Note • The "Stop Server" button is disabled when the option "Disable lmdown utility, use task manager" option is selected under "Edit Advanced Settings".

6. Click the **Server Status** tab.



Note • The server name or host name is case sensitive. Use the same name as provided in your license file.

7. On the Stop/Reread page, use the **Remote Server List** button to refresh the active server list. The server details are listed in the format Vendor_name: port@host.

Automatically Starting the License Server at System Startup


In order for `lmgrd` to start up automatically at system start-up time, you first must configure it as a service. Follow the procedure in [Configuring the License Server Manager as a Windows Service](#) before proceeding, and then continue with the steps below.



Task **To configure `lmgrd` as a service:**

1. With `lmtools` started and the desired service name selected, click the **Config Services** tab.

Figure 10-3: Config Services Tab



2. Make this license server manager a Windows service by selecting the **Use Services** check box.
3. Configure it to start at system startup time by selecting the **Start Server at Power Up** check box.



Note • On Windows platforms, it is best practice to set the location of `debug_Log_path` to a sub-folder of **ProgramData**. This location has user-write permissions by default, which are needed when the license server runs as a service with `LocalService` permission.

From now on, when the system is rebooted, this license server manager starts automatically as a Windows service.


Three-Server Setup in Imtools



Task *To start the service from the Imtools interface:*

1. Start Imtools and click the **Service/License File** tab.
2. Click the **Configuration using Services** option.
3. Select the service name from the list presented in the selection box. In this example, the service name is **DEMO License Manager**.

Figure 10-4: Service/License File Tab



4. Click the **Start/Stop/Reread** tab.
5. Start DEMO License Manager by clicking the **Start Server** button. DEMO License Manager license server starts and writes its debug log output to **c:\ProgramData\FNP_DIR\debuglog**.



Note • The "Stop Server" button is disabled when the option "Disable lmdown utility, use task manager" option is selected under "Edit Advanced Settings".


6. Click the **Server Status** tab.



Note • The server name or host name is case sensitive. Use the same name as provided in your license file.

7. lmttools now displays the triad details in the familiar format, where the top node represents the complete triad address (port@host1;port@host2;port@host3) and the leaf nodes are the primary, secondary and tertiary servers.

Figure 10-5: Stop/Reread Three server list and server details.



8. To shut down the triad, select the top node and click **ShutDown Server**.
9. To shut down a particular server in the triad, select the respective server and click **ShutDown**.

Migrating from `lmgrd` to `lmadmin`

A Fundamental Mode Change

The `lmadmin` license server manager combines all the functionality of the `lmgrd` license server manager with a Web-based, administrative interface. However, the `lmadmin` license server manager operates in some fundamentally different ways than the `lmgrd` license server manager.

The obvious change is that previous versions of the license server manager (`lmgrd`) used a command-line interface and the new license server manager (`lmadmin`) supports a browser-based client connection over HTTP. A more fundamental change in operation is that configuration options are now persistent—if you change settings and relaunch the tool, the previously set options stay in effect.

With `lmgrd`, the primary mode of operation is to run one instance of `lmgrd` for each vendor daemon where `lmgrd` obtains its configuration information from the command-line options used when the program is started, including the required specifying of a license file. To change settings you typically stop the license server, edit the license file and/or the script containing your command-line options, and relaunch the tool.

In contrast, the `lmadmin` license server manager is designed to:

- Support multiple vendor daemons with one `lmadmin` process.
- Launch without requiring any configuration options.
- Perform all server configuration and administration functions from the browser. (For special circumstances, the `lmutil` package provides additional functions.)
- Import existing license files (the new `lmadmin` license server manager is compatible with license files and vendor daemons produced using FlexNet Publisher 9.2 and later).
- Keep configuration options persistent.

Persistent configuration options is a significant change. Once set, settings remain in effect until changed. For example, if two vendor daemons are specified to use the same TCP port, only one will run. With `lmgrd`, this requires making changes to at least one of the license files as well as stopping and restarting the server. With `lmadmin`, you can change the TCP port for a vendor daemon while the license server is running. The manually specified port is then persistent and will remain as it was manually set the next time the license server is started, even if the license file is changed. The changes set in the license server manager override the license files.

Command Changes

Because of the changes in the fundamental operation of the system, many features have been redesigned. The following Imgrd command-line options are not supported by Imadmin.

Table 11-1 • Command-line options to Imgrd that are not supported by Imadmin.

Imgrd option	Imadmin notes
-2 -p	The replacement option is <code>-adminOnly yes</code> , which is the default for Imadmin.
-z	The replacement option is <code>-foreground</code> .
-c license_file_list	License files are now managed using either the license server management interface or the new <code>-import</code> option.
-v	Version information is now displayed in the license server management interface. The equivalent is <code>-version</code> option.
-l [+]<code>debug_log_path</code>	<p>The <code>-logDir</code> option defines the path to the debug log file (Imadmin.log) written by the Imadmin license server manager. The default location is <Imadmin_install_dir>/logs.</p> <p>The default location for the vendor daemon debug log files is <Imadmin_install_dir>/logs/<vendor>.log. The path to vendor daemon debug logs can be changed via either the Imadmin license management interface or the options file.</p> <p> Note • On Windows platforms, it is best practice to set the location of <code>debug_log_path</code> to a sub-folder of ProgramData. This location has user-write permissions by default, which are needed when the license server runs as a service with <code>LocalService</code> permission.</p>
-local	The replacement is to use the following argument settings: <code>-allowStopServer Yes -allowRemoteStopServer No</code>
-x Imdown	The replacement option is <code>-allowStopServer</code> . Note that the logical direction of this option has been reversed.
-x Imremove	The replacement option is <code>-allowLicenseReclaim</code> . Note that the logical direction of this option has been reversed.

Imadmin License Administration Functions

Imadmin provides some of the license administration functions previously provided by the command-line based license administration utilities or Imtools on the Windows platform. The following table lists functions provided within Imadmin that replace those provided by the license administration utilities.

Table 11-2 • Imadmin License Administration Functions

Imadmin Function	Description	Replaces Utility
Dashboard - Licenses	Displays details of licenses rights available and in use.	Imstat
Vendor Daemon Configuration - Administer - Stop	Stops the vendor daemon.	Imdown (in some usage cases)
Vendor Daemon Configuration - Administer - Reread License Files	Rereads license rights from license files included in the Imadmin configuration. Required only when the content of a license file is updated.	Imreread (see also Changes in Imreread Behavior when Using Imadmin)
Vendor Daemon Configuration - Administer - Rotate Report Logs	Switches the report log to a new file name.	Imswitchr
Server Configuration - Stop Server	Stops the license server. Note that Imadmin's default setting enables this button. To disable the button, start Imadmin with the -allowStopServer No argument.	Imdown (in some usage cases)

The following table details which command-line utilities may no longer be required and which utilities are required when using Imadmin.

Table 11-3 • Imadmin Use of License Administration Utilities

Utility	Required when using Imadmin
Imborrow	Yes, if using license rights in license files and borrow capability.
Imdiag	Yes, to diagnose license checkout problems.
Imdown	Not normally required.
Imhostid	Not normally required for Imadmin as it displays information about the system it is running on that includes the various identities normally used as hostids. Required for determining the hostids of client systems.
Iminstall	Yes, converts license files between different formats.
Imnewlog	Yes, if you use this function instead of Imswitchr to change to a new report log because you do not want to edit the report log file name in the options file.

Table 11-3 • Imadmin Use of License Administration Utilities

Utility	Required when using Imadmin
Impath	Yes, allows users direct control over license file path settings.
Imremove (in License File–Based Licensing)	Yes, releases a hung license to the pool of free licenses. Note that Imadmin’s default setting disables the operation of Imremove. To enable Imremove, start Imadmin with the -allowLicenseReclaim argument.
Imreread	Not normally required. See also Changes in Imreread Behavior when Using Imadmin .
Imstat	Only required to show additional information (such as borrow or reservations).
Imswitch	Yes, controls debug log location and size.
Imswitchr	Not required.
Imver	Yes, reports the version of a library or binary file. Note that you can determine the version of Imadmin by starting it with the -version argument.

Changes in Imreread Behavior when Using Imadmin

Normally Imreread is not required when using Imadmin, however if you use Imreread with Imadmin the following use cases are not supported:

- **Using Imreread to restart a vendor daemon**—When using Imgrd you can shut down a vendor daemon using Imdown and then use the Imreread command to restart the vendor daemon. The following sequence of commands will result in an error when using Imadmin:

```
Imdown -vendor demo  
Imreread -vendor demo
```
- **Using Imreread to load and start a new vendor daemon**—You can start Imgrd with a license file that specifies a vendor daemon and then replace this license file with one that includes information about a second vendor daemon. When Imreread is run, this second vendor daemon will be started. Using Imreread in this way with Imadmin will not load or start the vendor daemon. When using Imadmin, load and start a new vendor daemon as follows:
 1. To import a license file for the vendor daemon, go to the Administration page, open the Vendor Daemon Configuration tab, and click **Import License**.
 2. To start the vendor daemon, go to the Administration page, open the Vendor Daemon Configuration tab, and click **Administer** for the specific vendor daemon. Click **Start**.

Using License Administration Tools

License administration tools are available from the Flexera Software download site to help license administrators manage licenses and license servers. Always use the latest version of the utilities. If you are using `lmadmin` as your license server manager, then it provides functionality that replace some of these utilities. The table, [License Administration Utilities](#), lists these utilities and indicates when `lmadmin` provides an alternative.

Command-Line Utilities

All license server utilities are packaged as a single executable called `lmutil`. The `lmutil` is either installed as individual commands (either by creating links to the individual command names, or making copies of `lmutil` as the individual command names), or as a wrapper that runs the individual command as `lmutil` command. For example, `lmutil lmstat` or `lmutil lmdown`.

On Windows systems, the `lmutil` command form of the commands are available. There is also a graphical user interface available for these commands—see [lmtools \(Windows only\)](#).

Table 12-1 • License Administration Utilities

Utility	Description	lmadmin Function
lmborrow	Supports license borrowing.	None
lmdiag	Diagnoses license checkout problems.	None
lmdown	Gracefully shuts down selected vendor daemons on the license server (or on all three systems in the case of three-server redundancy).	Vendor Daemon Configuration - Administer - Stop
lmhostid	Reports the hostid of a system.	System Information displays hostids for the license server.
lminstall	Converts license files between different formats.	None

Table 12-1 • License Administration Utilities

Utility	Description	Imadmin Function
Imnewlog	Moves existing report log information to a new file name and starts a new report log file with existing file name.	None
Impath	Allows users direct control over license file path settings.	None
Imremove (in License File-Based Licensing)	Releases a hung license to the pool of free licenses.	None. Note Imadmin default setting disables Imremove.
Imremove (in Trusted Storage-Based Licensing)	Releases a hung license to the pool of free licenses in trusted storage.	None
Imreread	Causes the license daemon to reread the license file and start any new vendor daemons.	Vendor Daemon Configuration - Administer - Reread License Files
Imstat	Displays the status of a license server.	Dashboard - Licenses
Imswitch	Controls debug log location and size.	None
Imswitchr	Switches the report log to a new file name.	Vendor Daemon Configuration - Administer - Rotate Report Logs
Imver	Reports the version of a library or binary file.	None
Imvminfo	Returns the environment of the system used as to virtual or not.	None

- The Imvminfo utility introduced in the version 11.13.0 utilities.
- The Impath utility introduced in the version 7.0 utilities.
- The Imborrow utility introduced in the version 8.0 utilities.
- The Imswitch utility introduced in version 8.0 vendor daemon.
- The Imswitchr utility introduced in version 5.0 vendor daemon.

Common Arguments for Imutil

The following are valid arguments for most `lmutil` utilities:

Table 12-2 • Imutil Valid Arguments

Argument	Description
-c license_file_path	Most <code>lmutil</code> utilities need to know the path to the license file. This is specified with a <code>-c license_file_path</code> argument, or by setting the <code>LM_LICENSE_FILE</code> environment variable. Otherwise, the default location is used. The utilities also honor all <code>VENDOR_LICENSE_FILE</code> environment variables. Some utilities take more than one license file path in a license search path separated by colons on UNIX and semicolons on Windows. Pathnames that include spaces must be enclosed in double quotes.
-help	Displays usage information and exits.
-v	Displays the version of the utility and exits.
-verbose	Displays longer description for all errors found.



Note • The following information might be helpful:

- `VENDOR_LICENSE_FILE` environment variable is honored in utilities starting with version 7.0.
- The `-verbose` option was introduced in version 6.0 of the utilities.

Imborrow

The `lmborrow` utility supports the borrowing of those licenses that contain the `BORROW` attribute. This utility runs on the FlexEnabled client machine that borrows the licenses. The FlexEnabled application end users can use the utility to do the following:

- Initiate borrowing by setting the borrow period
- Clear the borrow period
- Purge expired licenses
- Determine borrow status
- Return a borrowed license early

Initiating Borrowing

To initiate borrowing, the end user of the FlexEnabled application sets the borrow period by running `lmborrow` from the command line or through `lmtools` on the FlexEnabled client machine.



Task **To initiate borrowing**

From the FlexEnabled client machine, enter the following command:

lmborrow {*vendor* | all} *enddate* [*time*]

where:

Table 12-3 • lmborrow Arguments for Initiating Borrowing

Argument	Description
<i>vendor</i>	The vendor daemon name that serves the licenses to be borrowed, or <code>all</code> specifies all vendor daemons in that license server.
<i>enddate</i> [<i>time</i>]	Date the license is to be returned in <code>dd-mm-yy</code> format. <i>time</i> is optional and is specified in 24-hour format (<code>hh:mm</code>) in the FlexEnabled application's local time. If <i>time</i> is unspecified, the checkout lasts until the end of the given end date.

For example, you might enter the following:

lmborrow sampled 20-aug-2017 13:00

This has the effect of setting `LM_BORROW` with the borrow period in either the registry (Windows) or in `$HOME/.flexlmborrow` (UNIX).

To borrow licenses for the desired vendor name, *on the same day and the same system* that the user runs `lmborrow`, run the applications to check out the licenses. If you run the applications more than once that day, no duplicate licenses are borrowed. No licenses are borrowed if the application is run on a day different than the date borrowing is initiated.

Aside from the `lmborrow` utility, you can use these other methods to initiate borrowing:

- Use the borrowing interface included in the FlexEnabled application, if such an interface is provided.
- Set the `LM_BORROW` environment variable directly.

See [Initiating License Borrowing](#) for more information on these other ways.

Clearing the Borrowed License Setting

End users of the FlexEnabled application can clear the `LM_BORROW` setting to stop licenses from being borrowed until borrowing is initiated again. For example, users might run `lmborrow -clear` after they have borrowed licenses for features that are used offline if—before disconnecting from the network—they want to run an application that checks out additional features, served by that *vendor name*, that are not meant to be borrowed. Clearing `LM_BORROW` does *not* change the status for already borrowed licenses.



Task **To clear the LM_BORROW setting in the Windows registry or in \$HOME/.flexlmborrow**

From the FlexEnabled client machine, enter the following command:

lmborrow -clear

Purging Expired Licenses

End users can remove expired borrowed licenses from their FlexEnabled client machine.



Task *To remove expired borrowed licenses*

From the FlexEnabled client machine, enter the following command:

Imborrow -purge



Tip • Combine this option with the `-status` option both to purge expired borrowed licenses from the client machine and to display information about the still valid borrowed licenses. See the next section [Determining Borrowed-License Status](#).

Determining Borrowed-License Status

End users can issue the following commands to display the status of licenses (vendor, feature name, and expiration date) currently borrowed by their FlexEnabled application.



Note • The current status of borrowed licenses is read from information stored on the client machine itself. Therefore, the client machine does not need to be connected to the network to obtain this information.



Task *To display the status of all currently borrowed features, expired or not*

From the FlexEnabled client machine, enter the following command:

Imborrow -status



Task *To purge expired borrowed licenses and display the status of non-expired borrowed licenses*

From the FlexEnabled client machine, enter the following command:

Imborrow -purge -status



Note • You can specify the `-purge` and `-status` options in any order. The result is always the same--expired borrowed licenses are removed and the status of the remaining borrowed licenses is displayed.

Returning a Borrowed License Early



Task **To return a borrowed license early**

1. Reconnect the FlexEnabled client to the network.
2. From the FlexEnabled client machine, issue the following command:

```
lmborrow -return [-c licfile] [-d display_name] [-u username] [-h hostname] [-fqdn] [-vendor name] feature [-bv version]
```

where:

Table 12-4 • lmborrow Arguments for Returning a Borrowed License Early

Argument	Description
-fqdn	Directs <code>lmborrow</code> to access the borrowing system using its fully qualified host name. Use this option if the license was borrowed based on the fully qualified host name, rather than the relative distinguished name. Use <code>lmstat</code> to determine the format of the host name used when the license was borrowed.
-c licfile	Use the specified license files. In some configurations, the license file needs to be specified in order to return the borrowed license early.
-d display	Used to specify the display from which the borrow was initiated. Required if your current display is different than what was used to initiate the borrow. On Windows, it is the system name or, in the case of a terminal server environment, the terminal server client name. On UNIX, it is in the form <code>/dev/ttyxx</code> or the X-Display name.
-u username	Used to specify the user name from which the borrow was initiated. In case of overridden user name use -u option to return the borrowed licenses early with the specified user.
-h hostname	Used to specify the host name from which the borrow was initiated. In case of overridden host name use -h option to return the borrowed licenses early with the specified hostname.
<i>feature</i>	The name of the borrowed feature to be returned early. Use <code>lmborrow -status</code> to get a list of borrowed feature names.
-bv [version]	Used to specify the version of the borrowed feature to return early. Use <code>lmborrow -status</code> to get the list of borrowed feature versions.

If the borrowing system is not placed back on the network before attempting the early return, the license is not returned and `LM_BORROW` is kept intact. Additionally, an error message is issued to the user with notification that the system needs to be connected to the network.



Note • Early borrowed license return was introduced in version 8.3 utilities.

lmdiag

lmdiag allows you to diagnose problems when you cannot check out a license.

Usage

```
lmdiag [-c license_file_list] [-n] [feature[:keyword=value]]
```

where:

Table 12-5 • lmdiag Argument Usage

Argument	Description
<code>-c license_file_list</code>	Diagnose the specified files.
<code>-n</code>	Run in non-interactive mode; lmdiag does not prompt for any input in this mode. In this mode, extended connection diagnostics are not available.
<code>feature</code>	Diagnose this feature only.
<code>keyword=value</code>	If a license file contains multiple lines for a particular feature, select a particular line for lmdiag to report on. For example: lmdiag f1:HOSTID=12345678 attempts a checkout on the line with the hostid "12345678." <i>keyword</i> is one of the following: VERSION, HOSTID, EXPDATE, KEY, VENDOR_STRING, ISSUER

If no *feature* is specified, **lmdiag** operates on all features in the license files in your list. **lmdiag** first prints information about the license, then attempts to check out each license. If the checkout succeeds, **lmdiag** indicates this. If the checkout fails, **lmdiag** gives you the reason for the failure. If the checkout fails because **lmdiag** cannot connect to the license server, then you have the option of running extended connection diagnostics.

These extended diagnostics attempt to connect to each TCP/IP port on the license server, and detects if the port number in the license file is incorrect. **lmdiag** indicates each TCP/IP port number that is listening, and if it is an `lmdadmin` or `lmgrd` process, **lmdiag** indicates this as well. If **lmdiag** finds the vendor daemon for the feature being tested, then it indicates the correct port number for the license file to correct the problem.

See Also

[FLEXLM_DIAGNOSTICS](#)

lmdown

The **lmdown** utility allows for the graceful shutdown of selected license daemons on all systems.

Usage

```
lmdown -c license_file_list [-vendor vendor_daemon] [-q] [-all] [-force]
```

where:

Table 12-6 • lmdown Argument Usage

Argument	Description
-c <i>license_file_list</i>	Use the specified license files. Note that specifying -c license_file_list is always recommended with lmdown .
-vendor <i>vendor_daemon</i>	Shut down only this vendor daemon. The license server continues running.
-q	Don't prompt. Otherwise, lmdown provides a confirmation prompt.
-all	If multiple servers are specified, automatically shuts down all of them. -q is implied with -all .
-force	If licenses are borrowed, lmdown runs only from the system where the license server is running, and then only if the user adds -force .

If **lmdown** encounters more than one server (for example if **-c** specifies a directory with many ***.lic** files) and **-all** is not specified, a choice of license servers to shut down is presented.



Note • On UNIX, do not use `kill -9` to shut down license servers. On Windows, if you must use the Task Manager to kill the FlexNet Licensing Service, be sure to end the `lmadmin` (or `lmgrd`) process first, then all the vendor daemon processes.

When using the `lmdown` utility to shut down license servers configured for three-server redundancy, there is a one-minute delay. You can protect the unauthorized execution of `lmdown` when you start up the license server manager.

See Also

[Downloading and Installing lmadmin](#)

[lmgrd Command-Line Syntax](#) for details about securing access to **lmdown**

Imhostid

The **Imhostid** utility returns the hostid of the current platform. Invoked without any arguments, **Imhostid** displays the default hostid type for the current platform. Otherwise, the hostid corresponding to the requested *type* is displayed, if supported on the current platform.

Usage

`lmhostid [-n] [-utf8] [-ptype argument] [hostid_type]`

Where:

Table 12-7 • lmhostid Argument Usage

Argument	Description
-n	Only the hostid, itself, is returned as a string, which is appropriate to use with HOSTID= in the license file. Header text is suppressed.

Table 12-7 • Imhostid Argument Usage

Argument	Description
hostid_type	<p>One of the following hostid types. If not specified, the default hostid for the current platform is displayed. See Hostids for Supported Platforms for a list of the default types.</p> <p>PLATFORM-DEPENDENT HOSTIDS</p> <ul style="list-style-type: none">• -ether—Ethernet address. <p></p> <p>Note • On Windows, Linux, and OS X platforms, this command returns all available addresses (active and inactive). For Windows and Linux platforms, these addresses include both teamed and non-teamed Ethernet interfaces. In general for teamed interfaces, the unique address for the team-bonding virtual adapter is returned. On Linux platforms, a separate (but same) virtual-adapter address is returned for each interface in the team. On Windows platforms, a single instance of the virtual-adapter address is returned for all teamed interfaces.</p> <ul style="list-style-type: none">• -string—String id.• -vsn—Volume serial number (Windows platforms only).• -flexid— USB FLEXID identification. This is applicable only for those platforms that support FlexNet ID dongles. See Obtaining System Hostids for a complete list.• -long—32-bit hostid.• -uuid—UUID binding value. Used with the -ptype command line option, shown under -ptype below. Only permitted with platform types (ptype) VM, or AMZN . <p>PLATFORM-INDEPENDENT HOSTIDS</p> <ul style="list-style-type: none">• -user—Current user name. Note that user names that contain spaces, for example 'test user' cannot be used in the Options file. Use the first word of the user name, for example 'test', in the Options file.• -display—Current display name. On Windows, it is the system name or, in the case of a terminal server environment, the terminal server client name. On UNIX, it is in the form /dev/ttyxx or the X-Display name.• -hostname—Current host name.• -hostdomain—Current host domain.• -internet—IP address of the machine in the format of the machine's protocol (IPv4 or IPv6). In a dual-stack environment, you can use the -v4 or -v6 switch to obtain the version-specific IP address (see the next bulleted items).

Table 12-7 • Imhostid Argument Usage

Argument	Description
hostid type	<ul style="list-style-type: none"> • -v4—Use with -internet to obtain the IPv4 address.
(continued)	<ul style="list-style-type: none"> • -v6—Use with -internet to obtain the IPv6 address.
	 <p>Tip • Both -v4 & -v6 are optional; using just -internet fetches the default IP address (usually IPv4). For more information, see Chapter 17, IPv6 Support, section Environment Variables on page 200, sub-section “FNP_IP_PRIORITY”.</p>
	 <p>Note • (Windows only) If a Windows machine is connected to a VPN, <code>Imhostid -internet</code> returns the virtual adapter IP address. To ensure that this command returns the physical adapter IP address during checkouts, perform this workaround: Run <code>regedit</code>, navigate to <code>HKEY_LOCAL_MACHINE\SYSTEM\CurrentControlSet\services\Tcpip\Linkage</code>, locate the <code>Bind</code> parameter, and edit the adapter order so that the physical adapter is listed first. Run <code>ipconfig/registerdns</code> to put the edit into effect.</p>
-utf8	The hostid is output as a UTF-8 encoded string rather than an ASCII string. If your hostid contains characters other than ASCII A through Z, a through z, or 0 through 9, use this option with <code>Imhostid</code> . To view a correct representation of the resulting hostid, use a utility, such as Notepad, that can display UTF-8 encoded strings.
-ptype	<p>(License-server binding in virtual environments only) Indicates the platform type. This option must be used in conjunction with a valid hostid binding type (see hostid_type).</p> <p>-ptype requires one of the following arguments, which then prefixes the generated hostid appropriately (as described):</p> <ul style="list-style-type: none"> • PHY—Physical machine only . Prefixes hostid with <code>PHY_</code>. • VM—Xen, VMware, or Hyper-V virtual platform. Prefixes hostid with <code>VM_</code>.

The following are examples of output from **Imhostid**:

```
Imhostid
```

```
Imhostid - Copyright (c) 1989-2016 Flexera Software LLC. All Rights Reserved.
```

```
The FlexNet host ID of this machine is ""00ff5018c189 0019d244e9fc 0016cfdaf65d 001558809422
005056c00001 005056c00008""
```

Only use ONE from the list of hostids.

```
Imhostid -ptype VM -uuid
```

```
Imhostid - Copyright (c) 1989-2016 Flexera Software LLC. All Rights Reserved.
```

```
The FlexNet host ID of this machine is "VM_UUID=0011223344556677889911bbccddeeff"
```

```
Imhostid -ptype PHY -display
```

```
Imhostid - Copyright (c) 1989-2016 Flexera Software LLC. All Rights Reserved.
```

```
The FlexNet host ID of this machine is "PHY_DISPLAY=sc-EXAMPLE"
```



Note • Some limitations exist with `hostid` reporting on virtual devices:

- **Ethernet hostids on Windows platforms** - From `lmutil` version 11.6.1 onwards, only the hostids of physical ethernet adapters are reported. Devices identified as virtual ethernet adapters are not reported as these identities are not permanent.
- **Physical (bare metal) hostids on virtual machines** - When run from a virtual machine, `lmhostid` cannot return hostids for the physical machine that hosts the virtual machine. To obtain hostids for the physical machine, `lmhostid` must be run from the Console OS.

See Also

[Hostids for Supported Platforms](#)

lminstall

The `lminstall` utility is designed primarily for typing in decimal format licenses to generate a readable format license file.

Usage

```
lminstall [-i in_lic_file] [-maxlen n] [-e err_file] [-o out_lic_file] \
          [-overfmt {2 | 3 | 4 | 5 | 5.1 | 6 | 7 | 7.1 | 8}] [-odecimal]
```

Normally, to convert from decimal to readable format, `lminstall` is used with no arguments; you are prompted for the name of the output license file. The default file name is today's date in **yyyymmdd.lic** format. Move this file to the application's default license file directory, if specified by the software publisher. Otherwise, use the `LM_LICENSE_FILE` or `VENDOR_LICENSE_FILE` environment variables to specify the directory where the ***.lic** files are located.

To finish entering, type **q** on a line by itself or enter two blank lines.

When an input file is specified with no output file specified, output goes to stdout; if neither input nor output file is specified, `lminstall` assumes that input comes from stdin and prompts the user for an output file name.

`lminstall` is also used to convert licenses from readable to decimal format and between different license versions.

To convert from readable to decimal:

```
lminstall -i in_lic_file -o out_lic_file -odecimal
```

To convert to v5.1 format:

```
lminstall -i in_lic_file -o out_lic_file -overfmt 5.1
```

To enforce a maximum line length of, for example, 50 characters:

```
lminstall -maxlen 50
```

Conversion errors are reported as necessary and can be written to a file by specifying `-e err_file`. `lminstall` has a limit of 1,000 lines of input.



Note • Decimal format is deprecated and is not supported.

Imnewlog

The `Imnewlog` utility switches the report log file by moving the existing report log information to a new file, then starting a new report log with the original report log file name. If you rotate report logs with `Imnewlog` instead of `Imswitchr`, you do not have to change the file name in the `REPORTLOG` line of the vendor daemon's option file. Requires a version 7.1 or later vendor daemon.

Usage

```
Imnewlog [-c license_file_list] feature renamed_report_Log [-secondary]
```

or:

```
Imnewlog [-c license_file_list] vendor renamed_report_Log [-secondary]
```

where:

Table 12-8 • Imnewlog Argument Usage

Argument	Description
<code>-c license_file_list</code>	Use the specified license files.
<code>feature</code>	Any feature in this license file.
<code>vendor</code>	name of the vendor daemon in this license file.
<code>renamed_report_Log</code>	New file path where existing report log information is to be moved.
<code>-secondary</code>	New report log file is generated on secondary server. <code>secondary</code> option switches the report log file by moving the existing report log information to a new file, then starting a new report log with the original report log file name at secondary server for 3-server setup.

Impath

The `Impath` utility allows direct control over license path settings. It is used to add to, override, or get the current license path settings.

Usage

```
Impath {-add | -override | -status} {vendor | all} license_file_list
```

where:

Table 12-9 • Impath Argument Usage

Argument	Description
<code>-add</code>	Prepends <code>license_file_list</code> to the current license search path or creates the license search path, if it doesn't exist, initializing it to <code>license_file_list</code> . Duplicates are discarded.

Table 12-9 • Impath Argument Usage

Argument	Description
-override	Overrides the existing license search path with <code>license_file_list</code> . If <code>license_file_list</code> is the null string, " ", the specified list is deleted. <ul style="list-style-type: none">● <code>Impath -override all ""</code>—Deletes the value of <code>LM_LICENSE_FILE</code>.● <code>Impath -override vendor ""</code>—Deletes the value of <code>VENDOR_LICENSE_FILE</code>.
-status	Displays current license path settings.
<i>vendor</i>	A vendor daemon name. Affects the value of <code>VENDOR_LICENSE_FILE</code> .
all	Refers to all vendor daemons. Affects the value of <code>LM_LICENSE_FILE</code> .
<i>license_file_list</i>	On UNIX, separate values with a colon. On Windows, separate values with a semicolon. If <code>license_file_list</code> is the null string, "", then the specified entry is deleted.



Note • *Impath* works by setting the registry entry on Windows or **\$HOME/.flexlmrc** on UNIX.

To display the current license path settings:

```
Impath -status
```

The following is displayed:

```
Impath - Copyright (c) 1989-2016 Flexera Software LLC.  
Known Vendors:
```

```
demo:  ./counted.lic:./uncounted.lic
```

```
Other Vendors:
```

```
/usr/local/flexlm/licenses/license.lic
```

Note that where the path is set to a directory, all the ***.lic** files are listed separately.

Imremove (in License File–Based Licensing)

The `Imremove` utility enables you to remove a single user’s license for a specified feature. If the application is active, it rechecks out the license shortly after it is freed by `Imremove`. Note that `Imadmin`’s default setting disables `Imremove`. To enable `Imremove`, start `Imadmin` with the `-allowLicenseReclaim` argument.

Usage

```
Imremove [-c license_file_list] feature user user_host display
```

or

`lmremove [-c license_file_list] -h feature server_host port handle`

Table 12-10 • lmremove in License file-based licensing Argument Usage

Argument	Description
<code>-c license_file_list</code>	Specify license files.
<code>-h</code>	Specify the license by its handle. Include <i>feature</i> , <i>server_host</i> , <i>port</i> , and <i>handle</i> with this argument.
<i>feature</i>	Name of the feature checked out by the user.
<i>user</i>	Name of the user whose license you are removing, as reported by <code>lmstat -a</code> .
<i>user_host</i>	Name of the host the user is logged into, as reported by <code>lmstat -a</code> .
<i>display</i>	Name of the display where the user is working, as reported by <code>lmstat -a</code> .
<i>server_host</i>	Name of the host on which the license server is running.
<i>port</i>	TCP/IP port number where the license server is running, as reported by <code>lmstat -a</code> .
<i>handle</i>	License handle, as reported by <code>lmstat -a</code> .

The *user*, *user_host*, *display*, *server_host*, *port*, and *handle* information must be obtained from the output of `lmstat -a`.

`lmremove` removes all instances of *user* on *user_host* and *display* from usage of *feature*. If the optional `-c license_file_list` is specified, the indicated files are used as the license file.

The `-h` variation uses the *server_host*, *port*, and license *handle*, as reported by `lmstat -a`. Consider this example `lmstat -a` output:

```
joe nirvana /dev/tty5 (v1.000) (cloud9/7654 102), start Fri 10/29 18:40
```

In this example, the user is **joe**, the user host is **nirvana**, the display is **/dev/tty5**, the server host is **cloud9**, the TCP/IP port is **7654**, and the license handle is **102**.

To remove this license, issue one of the following commands:

```
lmremove f1 joe nirvana /dev/tty5
```

or

```
lmremove -h f1 cloud9 7654 102
```

When removing by handle, if licenses are grouped as duplicates, all duplicate licenses are also removed. If license lingering is set and `lmremove` is used to reclaim the license, `lmremove` starts, but does not override, the license's linger time.

You can protect the unauthorized execution of `lmremove` when you start up `lmgrd`. The default for `lmadmin` is to disable `lmremove` because removing a user's license is disruptive.

See Also[Downloading and Installing Imadmin](#)[Imgrd Command-Line Syntax](#) for details about securing access to `Imremove`

Imremove (in Trusted Storage–Based Licensing)

License Administrator (LA) uses the `Imremove` utility to perform trusted storage borrow reclaim action when enabled by publisher. Note that `Imadmin`'s default setting disables `Imremove`. To enable `Imremove`, start `Imadmin` with the `-allowLicenseReclaim` argument.

Usage

```
Imremove <-c licfile> [-tsborrow <client_hostname>] | [-tsborrowstat]
```

where:

Table 12-11 • Imremove in trusted storage argument usage

Argument	Description
<code>-c</code>	Specifies both license file and port@host.
<code>-tsborrow</code>	Specifies trusted storage borrow reclaim, using this option along with client host name is mandatory.
<i>client host name</i>	The deduction record(s) associated with the hostname that could be reclaimed.
<code>tsborrowstat</code>	Specifies trusted storage borrow reclaim status. When this option is used, no borrow reclaim operation would be performed and borrow reclaim status would be displayed with the following information: <ul style="list-style-type: none"> • Number of licenses borrowed currently • Percentage borrow reclaim level • Count of reclaimed licenses • Number of borrow reclaims currently available

The `Imremove` utility allows the license administrator to perform borrow reclaim action by removing the deduction records from server trusted storage for the specified client host.

The publisher can enable this feature by setting appropriate values for the borrow reclaim percentage. By default, the reclaim percentage is set to 0 so the reclaim operation is not allowed.

The licenses activated or borrowed only from the activatable and hybrid license group can be reclaimed. Note that, the licenses obtained from concurrent license group cannot be reclaimed with this feature.

To be able to use the borrow reclaim feature, the `Imremove` utility should run on the same system as license server.

For example,

- borrow reclaim percentage is 10%
- total license count is 25

- client "nirvana" borrowed a license from server trusted storage
- client "cloud9" activated 2 licenses from server trusted storage

To view the borrow reclaim status on the license server, issue one of the following commands:

```
lmremove -c port@host -tsborrowstat
```

or

```
lmremove -c counted.lic -tsborrowstat
```

Output similar to following is displayed:

```
=== ACTIVATION BORROW RECLAIM STATUS ===  
Number of licenses borrowed currently: 24  
Percentage borrow reclaim level: 10%  
Count of reclaimed licenses:0  
Number of borrow reclaims currently available: 2
```

Number of borrow reclaims currently available = ((total number of deduction records * borrow reclaim percentage) – (count of reclaimed licenses) = (24 * 10%) – (0) = 2.4 rounded to 2.

Assume, the client host "nirvana" is lost or damaged.

To reclaim the borrow licenses issued for client host "nirvana", issue one of the following commands:

```
lmremove -c port@host -tsborrow "nirvana"
```

or

```
lmremove -c counted.lic -tsborrow "nirvana"
```

Output similar to the following is displayed:

```
lmremove: Successfully reclaimed (1) borrowed licenses(s) for the client "nirvana".
```

Now, view the borrow reclaim status, issue one of the following the commands:

```
lmremove -c port@host -tsborrowstat
```

or

```
lmremove -c counted.lic -tsborrowstat
```

Output similar to following is displayed:

```
=== ACTIVATION BORROW RECLAIM STATUS ===  
Number of licenses borrowed currently: 23  
Percentage borrow reclaim level: 10%  
Count of reclaimed licenses:1  
Number of borrow reclaims currently available: 1
```

Notice that, the count of reclaimed licenses is incremented by the number of deduction records that are reclaimed.



Note • When a reclaimed deduction record expires, the "Count of reclaimed licenses" is decremented by the one.

Assume, the client host "cloud9" is lost or damaged. To reclaim the borrow licenses issued for client host "cloud9", issue one of the following commands,

```
lmremove -c port@host -tsborrow "cloud9"
```

or

```
lmremove -c counted.lic -tsborrow "cloud9"
```

Output similar to following is displayed:

```
lmremove: Failed to perform activation borrow reclaim operation. (-205, 14100)
```

```
Failure reason: The requested activation borrow reclaim count (2) for client "cloud9" is greater than available reclaim count (1).
```

Assume, two more licenses are activated or borrowed. So, the number of deducted records is 25. Now, to reclaim the licenses issued for client host "cloud9" issue one of the following commands,

```
lmremove -c port@host -tsborrowstat
```

or

```
lmremove -c counted.lic -tsborrowstat
```

Output similar to following is displayed:

```
lmremove: Successfully reclaimed (2) borrowed licenses for the client "cloud9".
```

Now, to view the borrow reclaim status, issue one of the following commands,

```
lmremove -c port@host -tsborrowstat
```

or

```
lmremove -c counted.lic -tsborrowstat
```

Output similar to following is displayed:

```
=== ACTIVATION BORROW RECLAIM STATUS ===
```

```
Number of licenses borrowed currently: 23
```

```
Percentage borrow reclaim level: 10%
```

```
Count of reclaimed licenses: 3
```

```
Number of borrow reclaims currently available: 0
```

Now the borrowed reclaim level of 10% is reached so no more reclaims are allowed. To reclaim any more licenses, the license administrator creates an offline request to reset the reclaimed license count.

To reset the reclaimed license count, issue the following command and send the request.xml to publisher.

```
servercomptranutil -new request.xml reference=BorrowClaimReclaim
```

To process the reset response from publisher, issue the following command,

```
servercomptranutil -process response.xml
```

Now, view the borrow reclaim status, issue one of the following commands,

```
lmremove -c port@host -tsborrowstat
```

or

```
lmremove -c counted.lic -tsborrowstat
```

Output similar to following is displayed:

```
=== ACTIVATION BORROW RECLAIM STATUS ===  
Number of licenses borrowed currently: 23  
Percentage borrow reclaim level: 10%  
Count of reclaimed licenses: 0  
Number of borrow reclaims currently available: 2
```

Notice that, the count of reclaimed licenses is reset to 0 and the number of borrow reclaims currently available are two.

See Also

[Downloading and Installing lmadmin](#)
[lmgrd Command-Line Syntax](#) for details about securing access to `lmreread`

Imreread

The following description refers to the operation of `Imreread` with `Imgrd`.



Note • `Imadmin` includes functionality to read license files and start vendor daemons instead of using `Imreread`.

The `Imreread` utility causes the license server manager to reread the license file and start any new vendor daemons that have been added. In addition, all currently running vendor daemons are signaled to reread the license file and their options files for changes. If report logging is enabled, any report log data still in the vendor daemon's internal data buffer is flushed. `Imreread` recognizes changes to system host names, but cannot be used to change server TCP/IP port numbers.

If the optional vendor daemon name is specified, only the named daemon rereads the license file and its options file (in this case, `Imgrd` does not reread the license file).

Usage

```
Imreread [-c license_file_list] [-vendor vendor] [-all]
```

where:

Table 12-12 • `Imreread` Argument Usage

Argument	Description
<code>-c license_file_list</code>	Use the specified license files.
<code>-vendor vendor</code>	Only the vendor daemon, specified by the <code>vendor</code> option, rereads the license file and the options file. Additionally, <code>Imgrd</code> restarts <code>vendor</code> if necessary.
<code>-all</code>	If more than one <code>Imgrd</code> is specified, instructs all instances of <code>Imgrd</code> to reread.



Note • If you use the `-c license_file_list` option, the license files specified are read by `Imreread`, not by `Imgrd`; `Imgrd` rereads the file it read originally.

You can protect the unauthorized execution of `Imreread` when you start up the license server manager, `Imgrd`.



Note • Ability for vendor daemon to participate in rereading of its option file introduced in version 8.0 vendor daemon

See Also

[Downloading and Installing Imadmin](#)

[Changes in Imreread Behavior when Using Imadmin](#)

[Imgrd Command-Line Syntax](#) for details about securing access to `Imreread`

Imstat

The `Imstat` utility helps you monitor the status of all network licensing activities, including:

- Daemons that are running
- License files
- Users of individual features
- Users of features served by a specific vendor daemon
- BORROW licenses borrowed

The `lmstat` utility prints information that it receives from the license server; therefore, it does not report on unserved licenses such as uncounted licenses. To report on an uncounted license, the license must be added to a served license file and the application must be directed to use the license server for that license file (via `@host`, `port@host`, or `USE_SERVER`). Queued users and licenses shared due to duplicate grouping are also not returned by `lmstat`.

Usage

```
lmstat [-a] [-asec] [-c license_file_list] [-f [feature]] [-i [feature]] [-s[server]]
      [-S [vendor]] [-t timeout_value]
```

where:

Table 12-13 • lmstat Argument Usage

Argument	Description
<code>-a</code>	Displays all information. This option is a potentially expensive command. With many active users, this command option generates a lot of network activity.
<code>-asec</code>	Displays information in <code>hh:mm:ss</code> format.
<code>-c license_file_list</code>	Uses the specified license files.
<code>-f [feature]</code>	Displays users of <i>feature</i> . If <i>feature</i> is not specified, usage information for all features is displayed.
<code>-i [feature]</code>	Displays information from the feature definition line for the specified <i>feature</i> , or all features if <i>feature</i> is not specified.
<code>-s [server]</code>	Displays status of all license files listed in <code>\$VENDOR_LICENSE_FILE</code> or <code>\$LM_LICENSE_FILE</code> on <i>server</i> , or on all servers if <i>server</i> is not specified.
	 Note • Server name or host name is case sensitive, use the same name as provided in your license file.
<code>-S [vendor]</code>	Lists all users of <i>vendor</i> 's features.
<code>-t timeout_value</code>	Sets connection timeout to <i>timeout_value</i> . This limits the amount of time <code>lmstat</code> spends attempting to connect to <i>server</i> .

The output of `lmstat -a` looks similar to the following:

```

lmstat - Copyright (c) 1989-2016 Flexera Software LLC. All Rights Reserved.
Flexible License Manager status on Wed 01/11/2016 14:49
[Detecting lmgrd processes...]
License server status: 40000@prod
  License file(s) on prod: C:\prod\i86_n3\counted.lic

prod: license server UP v11.14.0
Feature usage info:
Users of f1: (Total of 4 licenses issued; Total of 1 license in use)
  "f1" v1.0, vendor: demo
  floating license
    daniel myhost2 19.36.18.26 (v1.0) (myhost1/40000 102), start Fri
      2/28 14:29
platforms: i86_n universal_mac x64_lsb,vendor_string: Flexera Software

where:

```

Table 12-14 • lmstat Output

Output	Argument	Description
daniel	<i>user</i>	User name.
myhost2	<i>user_host</i>	Host where user is running.
19.36.18.26	<i>display</i>	Display where user is running.
v1.0	<i>version</i>	Version of feature.
myhost1	<i>server_host</i>	Host where license server is running.
40000	<i>port</i>	TCP/IP port on <i>server_host</i> where license server is running.
102	<i>handle</i>	License handle.
start Fri 5/3 7:29	<i>checkout_time</i>	Time that this license was checked out.

The *user*, *user_host*, *display*, *server_host*, *port*, and *handle* information is used when removing licenses with `lmremove`.

lmswitch

The `lmswitch` utility switches the debug log file written by a particular vendor daemon by closing the existing debug log for that vendor daemon and starting a new debug log for that vendor daemon with a new file name. It also starts a new debug log file written by that vendor daemon if one does not already exist.

Usage

```
lmswitch [-c license_file_List] vendor new_debug_Log
```

where:

Table 12-15 • lmswitch Argument Usage

Argument	Description
<code>-c license_file_List</code>	Use the specified license files.
<code>vendor</code>	Vendor daemon in this license file.
<code>new_debug_Log</code>	Path to new debug log file.

By default, debug log output from the license server and all vendor daemons started by the server get written into the same debug file. `lmswitch` allows companies to keep separate log files for different vendor daemons and control the size of their debug log file.

If debug log output is not already directed to a separate file for this vendor daemon, `lmswitch` tells the vendor daemon to start writing its debug log output to a file, `new_debug_Log`. If this vendor daemon is already writing to its own debug log, `lmswitch` tells the vendor daemon to close its current debug log file and start writing its debug log output to `new_debug_Log`.



Note • The effect of `lmswitch` continues only until the vendor daemon is shut down or its options file is reread via `lmreread`. When the vendor daemon is restarted or its options file is reread, it looks for a `DEBUGLOG` line in the options file to determine whether or not to write its debug log output into its own file and, if so, what file to write. It is best practice to set the location of `new_debug_Log` to a `ProgramData` sub-folder, since this location has user-write permission by default, which is needed when the license server runs as a service with `LocalService` permission.

See Also:

[Downloading and Installing lmadm](#) for information on `lmadm` display `DEBUGLOG`
[Debug Log File](#)

Imswitchr

The `Imswitchr` utility switches the report log file by closing the existing report log and starting a new report log with a new file name. It also starts a new report log file if one does not already exist.

Usage

```
Imswitchr [-c license_file_list] feature new_report_Log
```

With version 5.0 or later vendor daemon, the command looks like this:

```
Imswitchr [-c license_file_list] vendor new_report_Log
```

where:

Table 12-16 • Imswitchr Argument Usage

Argument	Description
<code>-c license_file_list</code>	Use the specified license files.
<code>feature</code>	Any feature in this license file.
<code>vendor</code>	Vendor daemon in this license file.
<code>new_report_Log</code>	Path to new report log file.

If report logging is not enabled for the vendor daemon, `Imswitchr` tells it to start writing its report log output to `new_report_Log`. If report logging is already enabled for the vendor daemon, `Imswitchr` tells the vendor daemon to close its report log file and start writing its new report log output to `new_report_Log`.



Note • The effect of `Imswitchr` continues only until the vendor daemon is shut down or its options file is reread via `Imreread`. When the vendor daemon is restarted or its options file is reread, it looks for a `REPORTLOG` line in the options file to determine whether or not to write report log output to a file and, if so, what file to write. It is best practice to set the location of `new_report_Log` to a `ProgramData` sub-folder, since this location has user-write permission by default, which is needed when the license server runs as a service with `LocalService` permission

See Also:

[REPORTLOG](#)

[Imnewlog](#)

[Report Log File](#)

Imver

The **Imver** utility reports the version of a FlexNet Publisher library or binary file.

Usage

`Imver filename`

where *filename* is one of the following:

- The name of an executable file built with FlexNet Publisher
- The license server manager
- A license administration tool
- A vendor daemon

For example, if you have an application called **spell**, type **Imver spell**.

Imvminfo

The `Imvminfo` utility returns the environment as virtual or not.

Usage

`Imvminfo -Long`

Where `-Long` returns the following:

- Family of the virtual machine. The Family generally denotes the provider of the detected hypervisor software that the virtual machine (VM) is running on. Name denotes the

The virtual environments for which Family names are generated are:

Table 12-17 • List of VM_family and VM_name and hypervisor supported

Hypervisor	Family	Name
Hyper-V	MICROSOFT	HYPER-V
VMware Workstation	VMWARE	SERVER, Previously VMWARE
VMware ESXi	VMWARE	DESKTOP, Previously VMWARE
Oracle VirtualBox	VIRTUALBOX	VIRTUALBOX
Citrix XenServer	XEN	XEN
Amazon EC2	AMAZON	EC2
Parallels	PARALLELS	PARALLELS
QEMU-KVM	QEMU	QEMU-KVM

Table 12-17 • List of VM_family and VM_name and hypervisor supported

Hypervisor	Family	Name
Google Compute	GOOGLE	COMPUTE
Microsoft Azure	MICROSOFT	AZURE, previously HYPER-V

- Name of the virtual machine. The Name specifies the detected hypervisor product that the virtual machine (VM) is running on. The Name is for future use and is intended to be a subset of family.
- UUID of the machine
- GENID of the machine

For example, if you execute the command `lmvminfo -long`

```
C:\Users\Administrator\Desktop\Anita\leeds_stc1\64bit\x64_n6>lmvminfo.exe -long
```

```
lmvminfo - Copyright (c) 1989-2016 Flexera Software LLC. All Rights Reserved.
```

```
Running on Virtual Platform
```

```
FAMILY=VMWARE
```

```
NAME=VMWARE
```

```
UUID=0F064D56-465C-1286-6243-81C70C2766FF
```

```
GENID=433646c3cd09838f:39d695b09d953cb4
```



Note • If the GENID is not available then `GENID: ERROR - Unavailable` is displayed.

Imtools (Windows only)

The `lmtools` utility is a graphical user interface that allows you to administer the license server. This executable is available in the 32-bit and 64-bit Windows packages. Always use the newest version possible. You can get it from the software download site.

Some of the functions this utility performs include:

- Starting, stopping, and configuring license servers
- Getting system information, including hostids
- Getting server status

The `lmtools` utility has two modes in which to configure a license server:

- Configuration using a license file
- Configuration using services

On Windows Vista or later, you must run the `lmtools` utility as an administrator. If you do not run this executable as an administrator, the User Account Control (UAC) dialog will display as soon as it is started (as long as the UAC prompt is not disabled on the system).

Configuration Using License File

Operations are performed on a particular license file. The file can be either local or remote. In this mode, you cannot start the `lmadmin` or `lmgrd` process, but you can do everything else.



Task

To configure this mode:

1. Run the Imtools utility.
2. Click the **Configuration using License File** button.
3. Enter one or more the license file names or `port@host` specifications.

Configuration Using Services

Operations are performed on a service, which allows starting `lmadmin` or `lmgrd` processes local to the system on which `lmtools` is running. For details on configuring services, see [Configuring the License Server Manager as a Windows Service](#).

Limitation on File Path Lengths

The following file paths, used when configuring `lmtools`, are limited to 255 characters:

- Path to the **lmadmin.exe** or **lmgrd.exe** file
- Path to the license file
- Path to the debug log file

Ethernet hostids on Windows platforms

From version 11.6.1 onwards Imtools reports only the hostids of physical ethernet adapters. Devices identified as virtual ethernet adapters are not reported as these identities are not permanent.

Physical (Bare Metal) hostids on Virtual Machines

When run from a virtual machine, Imtools cannot return hostids for the physical machine that hosts the virtual machine. To obtain hostids for the physical machine `lmhostid` must be run from the Console OS.

Japanese User Identities

Imtools, when running on a system where native Microsoft `shift-jis` user identities are used, does not correctly display the user identity using non-ASCII, multi-byte (such as Japanese) characters. To display user identities correctly in multi-byte characters, use `lmstat` instead.

13

Managing the Options File

The options file allows the license administrator to control various operating parameters within the constraints of the license model. Users are identified by their user name, host name, display, IP address, or PROJECT (which is set with the LM_PROJECT environment variable).

For concurrent (floating) licenses, the license administrator can:

- Allow the use of features
- Deny the use of features
- Reserve licenses

The concurrent licenses can be held either in license files or in fulfillment records within trusted storage.

For activatable licenses, the license administrator can:

- Allow activation of licenses in a specific fulfillment record
- Deny activation of licenses in a specific fulfillment record

For all licenses, the license administrator can:

- Restrict the number of licenses available
- Control the amount of information logged about license usage
- Enable a report log file
- Control the automatic rereading of licenses

Options files allow you, as the license administrator, to be as secure or open with licenses as you like.

Lines in the options file are limited to 4000 characters. The \ character is the line-continuation character.



Note • *The following lists changes in the options file for FlexNet Publisher versions:*

- PROJECT identification (set by LM_PROJECT) in options file was introduced in the version 7.0 vendor daemon.

- Option file control for licenses held in fulfillment records in trusted storage was introduced in the 11.3 vendor daemon.
- `AUTOMATIC_REREAD` keyword introduced in the version 11.7 vendor daemon.

Creating an Options File



Task

To create an options file:

1. Use the appropriate options listed in [Options File Syntax](#) to create the options file for a vendor daemon using any text editor.
2. Locate the options file anywhere; however, it is recommended that the options file be placed in the same directory as the license file.
3. Add the path to the options file in the license file as the fourth field on the `VENDOR` line for the application's vendor daemon. For example:

```
VENDOR sampled /etc/sampled \
  [OPTIONS=]/sample_app/sampled/licenses/sampled.opt
```

enables the `sampled` vendor daemon to look at the specified options file.

If the path is omitted, the vendor daemon automatically looks for a file according to the following criteria:

- The name of the file is **vendor.opt**, where *vendor* is the vendor daemon name.
- The directory that contains the license file used by the license server manager.



Note • The default options file name, **vendor.opt**, was introduced in the version 6 vendor daemon.

Options File Syntax

The following is an overview of the available options. See [Options File Examples](#) for examples and additional information. Each line of the file controls one option.

Table 13-1 • Option Keywords

Option Keyword	Description
AUTOMATIC_REREAD	Turn off automatic reread of licenses at midnight.
ACTIVATION_LOWWATER	Controls the number of licenses that cannot be borrowed or transferred.
ACTIVATION_EXPIRY_DAYS	Controls the activation request based on the expiration dates mentioned in options file during activation.
BORROW_LOWWATER	Set the number of <code>BORROW</code> licenses that cannot be borrowed.

Table 13-1 • Option Keywords

Option Keyword	Description
DAEMON_SELECT_TIMEOUT	Defines the vendor daemon's timeout limit.
DEBUGLOG	Writes debug log information for this vendor daemon to the specified file (version 8.0 or later vendor daemon).
EXCLUDE	Deny a user access to a feature.
EXCLUDE_BORROW	Deny a user the ability to borrow BORROW licenses.
EXCLUDE_ENTITLEMENT	Deny a user the ability to activate licenses held in a fulfillment record in trusted storage.
EXCLUDEALL	Deny a user access to <i>all</i> features served by this vendor daemon.
FQDN_MATCHING	Sets the level of host name matching.
GROUP	Define a group of users for use with any options.
GROUPCASEINSENSITIVE	Sets case sensitivity for user and host lists specified in GROUP and HOST_GROUP keywords.
HOST_GROUP	Define a group of hosts for use with any options (version 4.0 or later).
INCLUDE	Allow a user to use a feature.
INCLUDE_BORROW	Allow a user to borrow BORROW licenses.
INCLUDE_ENTITLEMENT	Allow a user to activate licenses held in a fulfillment record in trusted storage.
INCLUDEALL	Allow a user to use <i>all</i> features served by this vendor daemon.
LINGER	Allow a user to extend the linger time for a feature beyond its check in.
MAX	Limit usage for a particular feature/group—prioritizes usage among users.
MAX_BORROW_HOURS	Changes the maximum borrow period for the specified feature.
MAX_OVERDRAFT	Limit overdraft usage to less than the amount specified in the license.
NOLOG	Turn off logging of certain items in the debug log file.
REPORTLOG	Specify that a report log file suitable for use by the FlexNet Manager license usage reporting tool be written.
RESERVE	Reserve licenses for a user or group of users/hosts.

Table 13-1 • Option Keywords

Option Keyword	Description
TIMEOUT	Specify idle timeout for a feature, returning it to the free pool for use by another user.
TIMEOUTALL	Set timeout on all features.

Comments

Include comments in your options file by starting each comment line with the hash symbol, #.

Specifying Features

When used within an options file entry, the feature name can be modified with an optional keyword-value pair to fully qualify it. This notation is used for distinguishing a particular group of licenses when there are multiple FEATURE lines for a single feature. The following syntax is used:

feature:keyword=value

For example:

`f1:VERSION=2.0`

specifies the version 2.0 pool of licenses for feature f1.

The following option keywords are used as feature name modifiers to denote a specific group of licenses:

- VERSION=
- HOSTID=
- EXPDATE=
- KEY=
- SIGN=
- ISSUER=
- NOTICE=
- VENDOR_STRING= (if configured by the publisher as a pooling component)
- dist_info=
- user_info=
- asset_info=

If the USER_BASED or HOST_BASED keywords appear in a feature line, this feature specification syntax must be used to qualify the feature.

Using a package name in place of a feature name applies the option to all of the components in the package.



Note • A colon (:) is a valid feature name character. If colons are in your feature names, specify a group of licenses with the following alternative syntax using quotation marks and spaces:

"feature keyword=value"

Specifying License Restrictions Using Type

Some option keywords restrict who may use licenses or where licenses may be used. These options take a type argument that specifies what the restriction is based on.

When using the option keywords EXCLUDE, EXCLUDE_ENTITLEMENT, EXCLUDEALL, EXCLUDE_BORROW, INCLUDE, INCLUDE_ENTITLEMENT, INCLUDEALL, INCLUDE_BORROW, MAX, and RESERVE, the following values can be used for type:

- **USER**—User name of the user executing the FlexEnabled application. User names are case sensitive and cannot contain spaces.

For the MAX option, you can also specify ALL_USERS as a value for the USER type. See [MAX](#) for details.

- **GROUP**—Name of the group of users executing the FlexEnabled application. (Before you can restrict an option by a specific group, the options file must also include a [GROUP](#) option that defines the group.)

For the MAX option, you can also specify ALL_GROUPS as a value for the GROUP type. See [MAX](#) for details.

- **HOST**—System host name or IP address where the application is executing. Host names are not case sensitive. The IP address can contain wildcard characters.

When using the option keywords EXCLUDE, EXCLUDEALL, EXCLUDE_BORROW, INCLUDE, INCLUDEALL, INCLUDE_BORROW, MAX, and RESERVE, the following values can be used for type:

- **DISPLAY**—Display where the application is displayed. On UNIX, DISPLAY is **/dev/ttyxx** (which is always **/dev/tty** when an application is run in the background) or the X-Display name. On Windows, it is the system name or, in the case of a terminal server environment, the terminal server client name. Display names are case sensitive.
- **INTERNET**—IP address of the system where the application is executing.
- **PROJECT**—LM_PROJECT environment variable set by the user who is executing the FlexEnabled application. Project names are case sensitive. See [Chapter 24, "Environment Variables,"](#) for more information about this variable.

On Windows (without terminal server), the HOST and DISPLAY names are both set to the system name. For licenses that allow checkouts from a terminal server (TS_OK keyword in the feature line), the USER, HOST, and DISPLAY names can be different from one another.

The types listed above take a single member. For example:

```
EXCLUDE coolsoft USER joe
```

To specify a list of users or hosts, first define the list using the GROUP or HOST_GROUP option lines, then use the [GROUP](#) or [HOST_GROUP](#) type to specify the group name. For example:

```
GROUP stars joe barbara susan
EXCLUDE coolsoft GROUP stars
```

- IP address as a HOST specification introduced in version 8 vendor daemon.
- Colons in feature names introduced in version 8 vendor daemon.

AUTOMATIC_REREAD

This option applies to all concurrent licenses held in license files or trusted storage.

`AUTOMATIC_REREAD OFF|ON`

Controls the automatic rereading of license files and trusted storage when any features are found to have expired. The default when this option is not set is that at midnight each day a check of each license is made to determine if it has expired. When any license is found to have expired, all license files and trusted storage are reread.

To turn off this automatic reread at midnight, enter `AUTOMATIC_REREAD OFF` in the options file.

ACTIVATION_LOWWATER

This option allows license administrator to control the number of hybrid and activatable license that cannot be borrowed or transferred. It works with a hybrid and activatable license in server side trusted storage.

Syntax

`ACTIVATION_LOWWATER entitlementID count`
`ACTIVATION_LOWWATER entitlementID:FID=fulfillmentID count`

For example, the server has an entitlement AAAA with 10 hybrid counts.

The following line in the options file allow only 4 licenses from entitlement AAAA to be borrowed or transferred to another license server.

```
ACTIVATION_LOWWATER AAAA 6
```

Table 13-2 • ACTIVATION_LOWWATER Terms

Term	Description
entitlementID	The entitlement Id originally used when requesting license activation.
Hybrid or Activatable count	Number of licenses that cannot be borrowed/transferred.
fulfillmentID (Optional)	A unique identity for this fulfillment record. Used to specify the fulfillment record to be returned.



Note • If more than one `ACTIVATION_LOWWATER` option for the same `EntitlementID` and `fulfillmentID` is specified in the options file, only the first one will be considered and the rest of duplicate entries will be discarded.

ACTIVATION_EXPIRY_DAYS

This option enables license administrators to control the activation request based on the expiration dates mentioned in the options file during activation. The publisher controls the activations based on the number of expiration days. If the expiration date is greater than the date set in the options file, the functionality is not successful.

`ACTIVATION_EXPIRY_DAYS entitlement ID days`

ACTIVATION_EXPIRY_DAYS entitlementID:FID=fulfillmentID days

Table 13-3 • ACTIVATION_EXPIRY_DAYS

Term	Description
entitlementID	The entitlement Id originally used when requesting license activation.
fulfillmentID (Optional)	A unique identity for this fulfillment record. Used to specify the fulfillment record to be returned.

For example, if there is more than one entry in the options file, the functionality works fine with respect to the first line given in the options file.

ACTIVATION_EXPIRY_DAYS ENTL-EZCALC 3

As per the example, if the current date is 11-December-2016 then the client can activate the license until 13-dec-2016. In case of normal activation without the options file, the client can borrow the license beyond 13-dec-2016.



Note • If more than one `ACTIVATION_EXPIRY_DAYS` option for the same `EntitlementID` and `FulfillmentID` with different count of days is mentioned in the options file, then the functionality always considers the first line and ignores subsequent lines.

BORROW_LOWWATER

This option is used for licenses held in license files. When licenses are available in trusted storage, activation is normally provided instead of BORROW.

`BORROW_LOWWATER feature[:keyword=value] n`

Sets the number of licenses for a BORROW feature that cannot be borrowed.

Table 13-4 • BORROW_LOWWATER Terms

Term	Description
feature	Name of feature being affected.
keyword=value	Feature name modifier to denote a group of licenses. See Also Specifying Features for details.
n	Number of licenses that cannot be borrowed via license borrowing.

For example, a feature f1 has a count of 10 and borrowing is enabled in the application and on the FEATURE line:

FEATURE f1 ... 10 ... BORROW SIGN=...

The following line in the options file allows only 7 licenses for this feature to be borrowed:

BORROW_LOWWATER f1 3

DAEMON_SELECT_TIMEOUT

DAEMON_SELECT_TIMEOUT *value_in_seconds*

Specifies the threshold for the amount of time (in seconds) that can elapse before a vendor-daemon connection experiences a timeout. The maximum value is **60**; the minimum is **1**.



Important • You can define the DAEMON_SELECT_TIMEOUT option only when the publisher has enabled it (that is, set the vendor variable `ls_support_custom_daemon_select_timeout` to **1**). Best practice is for publishers to enable DAEMON_SELECT_TIMEOUT only for environments that have limited bandwidth. If this option is not enabled, the timeout value for the vendor-daemon connection is 1 second, by default.

The following rules apply to DAEMON_SELECT_TIMEOUT:

- A value over 60 is always considered **60**.
- A value under 1 is always considered **1**.
- The default value is **1**.

DEBUGLOG

DEBUGLOG *[+]debug_log_path*

Specifies a location for the debug log output from the vendor daemon associated with this options file. Preceding the *debug_log_path* with a + character appends logging entries; otherwise, the file is overwritten each time the daemon is started. Note that this affects output from only the vendor daemon associated with this options file. The debug log output of the license server manager and any other vendor daemons in the same license file is not captured in this file.

On Windows, path names which include spaces have to be enclosed in double quotes. If **lmgrd** is started as a service, the debug log file is by default generated in the path specified in the options file. It is best practice to set the location of *debug_log_path* to a ProgramData sub-folder, since this location has user-write permission by default, which is needed when the license server runs as a service with LocalService permission.

See Also:

[Configuring the License Server Manager as a Windows Service](#)
[lmswitch](#)

[Debug Log File](#)—Debug log output restricted to that of just the vendor daemon introduced in version 8 vendor daemon.

EXCLUDE

This option applies to concurrent licenses held in license files and trusted storage.

EXCLUDE *feature[:keyword=value] type {name | group_name}*

Excludes a user or predefined group of users from the list of who is allowed to use the feature. EXCLUDE supersedes INCLUDE; conflicts between the EXCLUDE list and the INCLUDE list are resolved by the EXCLUDE taking precedence.

Table 13-5 • EXCLUDE Terms

Term	Description
<i>feature</i>	Name of the feature or package being affected.
<i>keyword=value</i>	Feature name modifier to denote a group of licenses. See “ Specifying Features ” for details.
<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP. See “ Specifying License Restrictions Using Type ” for details.
<i>name</i>	Name of an item of type <i>type</i> for which license usage is excluded.
<i>group_name</i>	Name of the group to exclude. Group names are case sensitive.

For example, the following option syntax excludes the user hank from the list of users able to use feature f1:

```
EXCLUDE f1 USER hank
```

EXCLUDE_BORROW

This option is used for licenses held in license files. When licenses are available in trusted storage, activation is normally provided instead of BORROW.

```
EXCLUDE_BORROW feature[:keyword=value] type \  
                {name | group_name}
```

Excludes a user or predefined group of users from the list of who is allowed to borrow licenses for this BORROW feature. EXCLUDE_BORROW supersedes INCLUDE_BORROW; conflicts between the EXCLUDE_BORROW list and the INCLUDE_BORROW list are resolved by the EXCLUDE_BORROW taking precedence.

Table 13-6 • EXCLUDE_BORROW Terms

Term	Description
<i>feature</i>	Name of the feature being affected.
<i>keyword=value</i>	Feature name modifier to denote a group of licenses. See Specifying Features for details.
<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.
<i>name</i>	Name of an item of type <i>type</i> for which license borrowing is excluded.
<i>group_name</i>	Name of the group to exclude from borrowing. Group names are case sensitive.

For example, the following option syntax excludes the user fred from the list of users able to borrow feature f1 (assuming the feature has the BORROW attribute):

```
EXCLUDE_BORROW f1 USER fred
```

EXCLUDE_ENTITLEMENT

This option only applies to licenses held in trusted storage and supplied using activation.

```
EXCLUDE_ENTITLEMENT entitlementId type {name | group_name}
```

Excludes a user or pre-defined group of users, etc., from the list of who is allowed to activate the licenses contained in a fulfillment record held in trusted storage. EXCLUDE_ENTITLEMENT supersedes INCLUDE_ENTITLEMENT; conflicts between the EXCLUDE_ENTITLEMENT list and the INCLUDE_ENTITLEMENT list are resolved by the EXCLUDE_ENTITLEMENT taking precedence.

Table 13-7 • EXCLUDE_ENTITLEMENT Terms

Term	Description
<i>entitlementId</i>	The entitlement Id used when requesting a license activation.
<i>type</i>	One of USER, HOST, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.
<i>name</i>	Name of an item of type <i>type</i> for which license usage is excluded.
<i>group_name</i>	Name of the group to exclude. Group names are case sensitive.

For example, the following option syntax excludes the user pete from the list of users able to activate licenses provided in the fulfillment record specified by the entitlement ID AB456:

```
EXCLUDE_ENTITLEMENT AB456 USER pete
```

EXCLUDEALL

This option applies to concurrent licenses held in license files and trusted storage.

```
EXCLUDEALL type {name | group_name}
```

Excludes a user or predefined group of users from the list of who is allowed to use all features served by this vendor daemon.

Table 13-8 • EXCLUDEALL Terms

Term	Description
<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.
<i>name</i>	Name of an item of type <i>type</i> for which license usage is excluded.
<i>group_name</i>	Name of the group to exclude. Group names are case sensitive.

For example, the following option syntax excludes any user on the system called chaos using all features served by this vendor daemon:

```
EXCLUDEALL HOST chaos
```

FQDN_MATCHING

This option applies to all licenses held in license files or trusted storage.

```
FQDN_MATCHING exact | lenient
```

Sets the level to which host names used in HOST type-specifiers must match the host name sent by the FlexEnabled application. The application is configured to send either its host name or its fully qualified domain name (FQDN) to the vendor daemon for validation with HOST type-specifiers. Check with your software publisher to determine fully qualified domain name support.

Table 13-9 • FQDN_MATCHING Terms

Term	Description
<i>exact</i>	The host name in the HOST type specifier must match in content and format to that sent by the application. This is the default setting.
<i>lenient</i>	The host name sent by the application needs to match to the extent supplied in the HOST type specifier or by the application, whichever is less restrictive.

Only the last FQDN_MATCHING keyword in the options file has effect; all others are ignored.

Table 13-10 shows the outcome of matching attempts between HOST type-specifiers in the options file and host names sent by the application.

Table 13-10 • Host Name Matching Matrix

Options File Settings		Application configured for FQDN—sends myhost.abc.com	Application not configured for FQDN—sends myhost
FQDN_MATCHING exact	INCLUDE <i>feature</i> HOST myhost	no	yes
	INCLUDE <i>feature</i> HOST myhost.abc.com	yes	no
FQDN_MATCHING lenient	INCLUDE <i>feature</i> HOST myhost	yes	yes
	INCLUDE <i>feature</i> HOST myhost.abc.com	yes	yes

Examples

Consider the following example that demonstrates restrictive host name matching:

```
INCLUDE f1 HOST myhost.abc.com
```

```
FQDN_MATCHING exact
```

This includes **myhost.abc.com** on the list of hosts able to use feature f1. Furthermore, the host name sent by the application must be a fully qualified domain name that matches **myhost.abc.com** exactly.

In contrast, consider this example, which is less restrictive:

```
INCLUDE f2 HOST myhost.abc.com
```

```
FQDN_MATCHING lenient
```

This includes **myhost.abc.com** on the list of hosts able to use feature f2. The license rights are authenticated and a checkout allowed if any of the following match:

- The FQDN - **myhost.abc.com**
- The host name - **myhost**
- The domain name - **.abc.com**

The example below is even more lenient:

```
INCLUDE f2 HOST myhost
```

```
FQDN_MATCHING lenient
```

This includes the host name, **myhost**, on the list of hosts for feature f3. Since lenient matching is specified, host names such as **myhost**, **myhost.abc.com**, and **myhost.xyz.com** match, whereas **yourhost** or **yourhost.abc.com** do not match.

See Also

[“Specifying License Restrictions Using Type”](#)

FQDN_MATCHING introduced in version 9.3 client library and vendor daemon.

GROUP

```
GROUP group_name user_List
```

Defines a group of users for use in INCLUDE, INCLUDEALL, INCLUDE_ENTITLEMENT, EXCLUDE, EXCLUDEALL, EXCLUDE_ENTITLEMENT, and RESERVE option lines.

Table 13-11 • GROUP Terms

Term	Description
<i>group_name</i>	Name of the group being defined. Group names are case sensitive.
<i>user_list</i>	List of user names in that group. Names are case sensitive and cannot contain spaces. Set the GROUPCASEINSENSITIVE options file keyword to turn on case insensitivity. See GROUPCASEINSENSITIVE .

To create a large user group, define several GROUP lines each containing up to the maximum of 4,000 characters. All the users will be placed in a single group: Multiple GROUP lines for the same group name add all the specified users into the group.

For example, the following option syntax defines the group Hackers consisting of bob, howard, and james:

```
GROUP Hackers bob howard james
```



Note • USER_GROUP is an alias for GROUP.

GROUPCASEINSENSITIVE

```
GROUPCASEINSENSITIVE OFF|ON
```

If set to **ON**, user names and host names specified with the options file GROUP and HOST_GROUP keywords, respectively, are treated as case-insensitive.

By default, GROUPCASEINSENSITIVE is **OFF**, and user and host names are treated as case-sensitive.

HOST_GROUP

`HOST_GROUP group_name host_list`

Defines a group of hosts for use in `INCLUDE`, `INCLUDEALL`, `INCLUDE_ENTITLEMENT`, `EXCLUDE`, `EXCLUDEALL`, `EXCLUDE_ENTITLEMENT`, and `RESERVE` option lines. Multiple `HOST_GROUP` lines add all the specified hosts into the group.

Table 13-12 • `HOST_GROUP` Terms

Term	Definition
<i>group_name</i>	Name of the group being defined. Host group names are case sensitive.
<i>host_list</i>	List of host names in that group. Names are case sensitive. Set the <code>GROUPCASEINSENSITIVE</code> options file keyword to turn on case insensitivity. See GROUPCASEINSENSITIVE .

For example, the following option syntax defines the host group `Pacific` consisting of `tokyo`, `seattle`, and `auckland`:

```
HOST_GROUP Pacific tokyo seattle auckland
```

Anywhere a host name can be used in an options file, an IP address can be used instead.

INCLUDE

This option applies to concurrent licenses held in license files and trusted storage.

`INCLUDE feature[:keyword=value] type {name | group_name}`

Includes a user or predefined group of users in the list of who is allowed to use licenses for this feature. Any user who is not in an `INCLUDE` or `INCLUDEALL` statement is not allowed to use that feature. `EXCLUDE` supersedes `INCLUDE`; conflicts between the `EXCLUDE` list and the `INCLUDE` list are resolved by the `EXCLUDE` taking precedence.

Table 13-13 • `INCLUDE` Terms

Term	Definition
<i>feature</i>	Name of the feature or package being affected.
<i>keyword=value</i>	Feature name modifier to denote a group of licenses. See Specifying Features for details.
<i>type</i>	One of <code>USER</code> , <code>HOST</code> , <code>DISPLAY</code> , <code>INTERNET</code> , <code>PROJECT</code> , <code>GROUP</code> , or <code>HOST_GROUP</code> . See Specifying License Restrictions Using Type for details.
<i>name</i>	Name of an item of type <code>type</code> for which license usage is included.
<i>group_name</i>	Name of the group for which license usage is included. Group names are case sensitive.

To include user `bob` in the list of users able to use feature `f1`:

```
INCLUDE f1 USER bob
```

The include list is created from all the INCLUDEALL and INCLUDE lines in the options file.



Note • INCLUDE is required for USER_BASED or HOST_BASED features. The license administrator specifies which users are allowed to use the product, via INCLUDE, and the license limits the number of users that are INCLUDED. In a USER_BASED or HOST_BASED license model, users (or predefined groups of users) who are not listed with the INCLUDE keyword cannot check out a license.

INCLUDE_BORROW

This option is used for licenses held in license files. When licenses are available in trusted storage, normally activation is provided instead of BORROW.

```
INCLUDE_BORROW feature[:keyword=value] type {name | group_name}
```

Includes a user or predefined group of users in the list of who is allowed to borrow the BORROW feature. Anyone not in an INCLUDE_BORROW statement is not allowed to borrow licenses. EXCLUDE_BORROW supersedes INCLUDE_BORROW; conflicts between the EXCLUDE_BORROW list and the INCLUDE_BORROW list are resolved by the EXCLUDE_BORROW taking precedence.

Table 13-14 • INCLUDE_BORROW Terms

Term	Definition
feature	Name of the feature and package being affected. Specify the package name and the feature name or specify only the package name.
keyword=value	Feature name modifier to denote a group of licenses. See Specifying Features for details.
type	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.
name	Name of an item of type <i>type</i> for which license borrowing is included.
group_name	Name of the group for which license borrowing is included. Group names are case sensitive.

For example, the following option syntax includes user tom in the list of users able to borrow feature f1:

```
INCLUDE_BORROW f1 USER tom
```



Note • For USER_BASED or HOST_BASED features a user or predefined group of users must be on both an INCLUDE list and an INCLUDE_BORROW list to borrow a feature.

INCLUDE_ENTITLEMENT

This option only applies to licenses held in trusted storage.

```
INCLUDE_ENTITLEMENT entitlementId type {name | group_name}
```

Includes a user or predefined group of users in the list of who is allowed to activate the licenses contained in a fulfillment record held in trusted storage. EXCLUDE_ENTITLEMENT supersedes INCLUDE_ENTITLEMENT; conflicts between the EXCLUDE_ENTITLEMENT list and the INCLUDE_ENTITLEMENT list are resolved by the EXCLUDE_ENTITLEMENT taking precedence.

Table 13-15 • INCLUDE_ENTITLEMENT Terms

Term	Definition
<i>entitlementId</i>	The entitlement Id originally used when requesting a license activation.
<i>type</i>	One of USER, HOST, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.
<i>name</i>	Name of an item of type <i>type</i> for which license usage is included.
<i>group_name</i>	Name of the group to include. Group names are case sensitive.

For example, the following option syntax includes the user `claire` in the list of users able to activate licenses provided in the fulfillment record specified by the entitlement Id `AB456`:

```
INCLUDE_ENTITLEMENT AB456 USER claire
```

Example for Include variations with hybrid trusted storage:

This example demonstrates the behavior of **INCLUDE**, **INCLUDE_BORROW** and **INCLUDE_ENTITLEMENT** on *feature F1*. *F1* originates from a served trusted storage hybrid license with *EntitlementID ENTLID1*.

Table 13-16 • Example for INCLUDE, INCLUDE_BORROW, INCLUDE_ENTITLEMENT

Option file	Contains	Behavior
INCLUDE	F1 USER John	concurrent checkout limited to John? Yes certificate borrow limited to John? Yes activation borrow limited to John? No
INCLUDE_BORROW	F1 USER John	concurrent checkout limited to John? No certificate borrow limited to John? Yes activation borrow limited to John? No
INCLUDE	F1 USER John INCLUDE_ENTITLEMENT ENTLID1 USER John	concurrent checkout limited to John? Yes certificate borrow limited to John? Yes activation borrow limited to John? Yes

Table 13-16 • Example for INCLUDE, INCLUDE_BORROW, INCLUDE_ENTITLEMENT

Option file	Contains	Behavior
INCLUDE_ENTITLEMENT	ENTLID1 USER John	concurrent checkout limited to John? No certificate borrow limited to John? No activation borrow limited to John? Yes

Another example: *ENTLID12* contains hybrid features *F1* and *F2*. The following options file allows only John to perform concurrent checkout, certificate borrow or activation borrow on all *ENTLID12*'s features:

```
INCLUDE F1 USER John
INCLUDE F2 USER John
INCLUDE_ENTITLEMENT ENTLID12 USER John
```



Note • activation borrow always activates all features from an entitlement

INCLUDEALL

This option applies to concurrent licenses held in license files and trusted storage.

```
INCLUDEALL type {name | group_name}
```

Includes a user or predefined group of users in the list of who is allowed to use all features served by this vendor daemon.

Table 13-17 • INCLUDEALL Terms

Term	Definition
type	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.
name	Name of an item of type <i>type</i> for which license usage is included.
group_name	Name of the group to include. Group names are case sensitive.

For example, the following option syntax allows the user jane to use all features served by this vendor daemon:

```
INCLUDEALL USER jane
```

The include list is created from all the INCLUDEALL and INCLUDE lines in the options file.

LINGER

This option applies to concurrent licenses held in license files and trusted storage.

LINGER *feature[:keyword=value] seconds*

A lingering license stays checked out for a specified period of time beyond its checkin or FlexEnabled application exit, whichever comes first. The linger time may have been configured by the software publisher in the FlexEnabled application. When this is the case, then the longer linger time is applied. Thus you can set a longer linger time than configured by the software publisher but not shorten the linger time.

Table 13-18 • LINGER Terms

Term	Definition
<i>feature</i>	Name of the feature.
<i>keyword=value</i>	Feature name modifier to denote a group of licenses. See Specifying Features for details.
<i>seconds</i>	Number of seconds the license lingers. The software publisher sets a minimum value. If you specify a value for <i>seconds</i> that is smaller than the minimum, the minimum is used.

For example, the following option syntax sets the linger value for feature f1 to one hour (3600 seconds):

```
LINGER f1 3600
```

The actual linger time varies somewhat since the vendor daemon checks all lingering licenses just once per minute. Also if a new license request is made that would otherwise be denied, a check of the lingering licenses is made immediately to attempt to satisfy the new request.

MAX

This option applies to concurrent licenses held in license files and trusted storage.

MAX *num_lic feature[:keyword=value] type {name | group_name}*

Limits usage for a group or user.

Table 13-19 • MAX Terms

Term	Description
<i>num_lic</i>	Usage limit for this user or group.
<i>feature</i>	Feature or package this limit applies to.
<i>keyword=value</i>	Feature name modifier to denote a group of licenses. See Specifying Features for details.
<i>type</i>	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.

Table 13-19 • MAX Terms

Term	Description
<i>name</i>	Name of an item of type <i>type</i> for which usage is limited. To avoid having to repeat the MAX line multiple times to restrict all users, you can use one MAX line that specifies ALL_USERS as the value for the type USER (for example, USER ALL_USERS). See for USER and GROUP Examples more information.
<i>group_name</i>	Name of the group to limit. Group names are case sensitive. (The options file must include a GROUP line that defines this group.) To avoid having to repeat the MAX line multiple times to restrict all groups defined in the options file, you can use one MAX line that specifies ALL_GROUPS as the value for the type GROUP (for example, GROUP ALL_GROUPS). See for USER and GROUP Examples more information.

USER and GROUP Examples

The following are examples of using the USER and GROUP types for the MAX option.



Note • Never position a MAX line that restricts USER *user_name* for a specific feature after a MAX line that restricts USER ALL_USERS for the same feature. Likewise, never position a MAX line that restricts GROUP *group_name* for a specific feature after a MAX line that restricts GROUP ALL_GROUPS for the same feature. The positioning invalidates the restriction in the later line.

- To limit the user jan to five licenses for feature f1, include the following line in the options file:
`MAX 5 f1 USER jan`
- To limit all users to to five licenses for feature f1, include the following line:
`MAX 5 f1 USER ALL_USERS`
- To limit the user jan to five licenses for feature f1 and all other users to four licenses for the same feature, include the following lines:
`MAX 5 f1 USER jan`
`MAX 4 f1 USER ALL_USERS`
- To limit group DEV to three license for feature f2 and all other groups to one license for the same feature, include these lines:
`MAX 3 f2 GROUP DEV`
`MAX 1 f2 GROUP ALL_GROUPS`
- If you attempt to position a MAX line that specifies ALL_USERS (or ALL_GROUPS) before a MAX line that specifies a single user (or single group), FlexNet Publisher cannot enforce the restriction in the second line because the user or group in the second line (in this case, the DEV group) is a part of ALL_USERS or ALL_GROUPS in the first line.

For example, the following line positioning is *invalid*:
`MAX 1 f2 GROUP ALL_GROUPS`
`MAX 3 f2 GROUP DEV`

Queueing Behavior When Requested Licenses Exceed MAX Limit

For current version vendor daemons, if queuing is allowed by the application, requests for licenses that exceed the limit set by the MAX keyword will be denied. From the above example, if the user jan requests six licenses for feature f1, the request will be denied. Requests from users or groups within the MAX limit that exceed the number of available licenses will be queued. For example, if the license file includes ten licenses for feature f1 and nine of those licenses are already checked out, a request from the user jan for two licenses will be queued.

MAX_BORROW_HOURS

This option is used for licenses held in license files. When licenses are available in trusted storage, normally activation is provided instead of BORROW.

MAX_BORROW_HOURS *feature[:keyword=value] num_hours*

Changes the maximum period a license can be borrowed from that specified in the license file for *feature*. The new period must be less than that in the license file. If multiple MAX_BORROW_HOURS keywords appear in the options file, only the last one is applied to *feature*.

Table 13-20 • MAX_BORROW_HOURS Terms

Term	Description
<i>feature</i>	Feature this borrow period applies to. The <i>feature</i> must have BORROW enabled.
<i>keyword=value</i>	Feature name modifier to denote a group of licenses. See Specifying Features for details.
<i>num_hours</i>	Number of hours in the new borrow period. This value must be less than that specified in the license file for feature (the default, if not specified, is 168 hours).

MAX_OVERDRAFT

This option applies to concurrent licenses held in license files and trusted storage.

MAX_OVERDRAFT *feature[:keyword=value] num_lic*

Limits OVERDRAFT license usage below the OVERDRAFT allowed by the license file.

Table 13-21 • MAX_OVERDRAFT Terms

Term	Description
<i>feature</i>	Feature this limit applies to.
<i>keyword=value</i>	Feature name modifier to denote a group of licenses. See Specifying Features for details.
<i>num_lic</i>	Usage limit for this user or group.

NOLOG

NOLOG {IN | OUT | DENIED | QUEUED | UNSUPPORTED}

Suppresses logging the selected type of event in the debug log file.

Table 13-22 • NOLOG Terms

Entry	Description
NOLOG IN	Turns off logging of checkins. Two separate NOLOG lines are required to turn off logging of checkouts and queued requests.
NOLOG OUT	Turns off logging of checkouts.
NOLOG DENIED NOLOG QUEUED	Turns off logging of checkouts and queued requests. License administrators use this option to reduce the size of the debug log file. However, it can reduce the usefulness of the debug log when debugging license server problems.
NOLOG UNSUPPORTED	Suppresses UNSUPPORTED messages in the debug log. This suppresses error messages in the debug log that report a failure due to the feature being unsupported.

See Also

[lmswitch](#)

REPORTLOG

REPORTLOG [+]*report_log_path*

REPORTLOG specifies the report log file for this vendor daemon. It is recommended preceding the *report_log_path* with a + character to append logging entries; otherwise, the file is overwritten each time the daemon is started.

On Windows, path names that include spaces have to be enclosed in double quotes. If **lmgrd** is started as a service, the default location for the report log file is the current working directory unless a fully qualified path is specified.



Note • *FlexNet Manager is a separate product available from Flexera Software, it is used to process report log files. FlexNet Manager processes only report log files, not debug log files. On Windows, It is best practice to set the location of report_log_path to a ProgramData sub-folder, since this location has user-write permission by default, which is needed when the license server runs as a service with LocalService permission*

Reporting on Projects with LM_PROJECT

The FlexNet Manager report writer reports on projects. A project is set up by having all users working on the same project set their LM_PROJECT environment variable (or registry on Windows) to a string that describes the project. FlexNet Manager groups usage by project, as defined by what LM_PROJECT was set to when the application was run.

See Also

Configuring the License Server Manager as a Windows Service
 Environment Variables
 Report Log File

RESERVE

This option applies to concurrent licenses held in license files and trusted storage.

```
RESERVE num_lic feature[:keyword=value] type {name | group_name}
```

Reserves licenses for a specific user.

Table 13-23 • RESERVE Terms

Term	Description
num_lic	Number of licenses to reserve for this user or group.
feature	Feature or package this reservation applies to.
keyword=value	Feature name modifier to denote a group of licenses. See Specifying Features for details.
type	One of USER, HOST, DISPLAY, INTERNET, PROJECT, GROUP, or HOST_GROUP. See Specifying License Restrictions Using Type for details.
name	Name of an item of type <i>type</i> for which license usage is reserved.
group_name	Name of group for which license usage is reserved. Group names are case sensitive.

For example, the following option syntax reserves one license of feature f1 for user mel:

```
RESERVE 1 f1 USER mel
```

If you want to reserve a license for *each* of several users or groups, you must use a separate RESERVE line for each user or group. If a package name is specified, all components that comprise the package are reserved.

The RESERVE keyword should not be used on packages and package suites that also use the SUITE_RESERVED option. The RESERVE keyword in the options file includes static information about the reservation policy. The SUITE_RESERVED option reserves a set of package components. Once one package component is checked out, all the other components are reserved for that same user. When the license keys are checked out by a user, the SUITE_RESERVED option within the Package will dictate additional reservation policy which can dynamically change depending on the product usage pattern. Because these options present conflicting reserve parameters, they can not be used together. The total number of reservations supported per options file is 10000.



Note • Any licenses reserved for a user are dedicated to that user. Even when that user is not actively using the license, it is unavailable to other users. However, a RESERVED license does not cause usage to be reported by FlexNet Manager if the license is not actually in use.

TIMEOUT

This option applies to concurrent licenses held in license files and trusted storage.

`TIMEOUT feature[:keyword=value] seconds`

Sets the time after which an inactive license is freed and reclaimed by the vendor daemon.



Note • The software publisher must have enabled this feature in the FlexEnabled application for it to work. Contact your software publisher to find out if this feature is implemented.

Table 13-24 • TIMEOUT Terms

Term	Description
feature	Name of the feature.
keyword=value	Feature name modifier to denote a group of licenses. See Specifying Features for details.
seconds	Number of seconds after which inactive license is reclaimed. The software publisher sets a minimum value. If you specify a value for <i>seconds</i> that is smaller than the minimum or greater than the minimum, the greater value is used.

For example, the following option syntax sets the timeout for feature f1 to one hour (3600 seconds):

```
TIMEOUT f1 3600
```

TIMEOUT checks in the licenses if the FlexEnabled application has been inactive for a period longer than the specified time period. The daemon declares a process inactive when it has not received heartbeats from it whereas an active FlexEnabled application sends heartbeats. A TIMEOUT line must be present in the options file in order to take advantage of this feature.

TIMEOUTALL

This option applies to concurrent licenses held in license files and trusted storage.

`TIMEOUTALL seconds`

Same as TIMEOUT, but applies to all features.

How the Vendor Daemon Uses the Options File

When the vendor daemon is started by `lmadmin` or `lmgrd`, the vendor daemon reads its options file. There is only one options file per vendor daemon and each vendor daemon needs its own options file. For any changes in an options file to take effect, the vendor daemon must read its options file. The `lmreread` utility causes the vendor daemon to reread its options file.

The **Imrread** utility enhanced in version 8.0 vendor daemon so that it causes the vendor daemon to reread the options file. If you are using earlier versions, the vendor daemon must be stopped and restarted in order for the options file to be reread.

Rules of Precedence in Options Files

Rules of precedence take effect when **INCLUDE** and **EXCLUDE** statements are combined in the same options file and control access to the same feature (in license files) or fulfillment record (in trusted storage). The following define the precedence when both types of statements appear together:

- If there is only an **EXCLUDE** list, everyone who is not on the list is allowed to use the feature.
- If there is only an **INCLUDE** list, only those users on the list are allowed to use the feature.
- If neither list exists, everyone is allowed to use the feature.
- The **EXCLUDE** list is checked before the **INCLUDE** list; someone who is on both lists is not allowed to use the feature.

Once you create an **INCLUDE** or **EXCLUDE** list, everyone else is *implicitly* outside the group. This feature allows you, as a license administrator, the ability to control licenses without having to *explicitly* list each user that you wish to allow or deny access to. In other words, there are two approaches; you either:

- Give most users access and list only the exceptions, or
- Severely limit access and list only the those users that have access privileges

Options File Examples

The following information gives some examples of options files intended to illustrate ways to effectively control access to your licenses.

Simple Options File Example

```
RESERVE 1 compile USER robert
RESERVE 3 compile HOST mainline
EXCLUDE compile USER lori
NOLOG QUEUED
```

This options file restricts the use of concurrent licenses as follows:

- Reserves one license for the feature `compile` for the user `robert`.
- Reserves three licenses for the feature `compile` for anyone on the system with the host name `mainline`.
- Prevents the user `lori` from using the `compile` feature on any system on the network.
- Causes `QUEUED` messages to be omitted from the debug log file.

The sum total of the licenses reserved must be less than or equal to the number of licenses specified in the **FEATURE** line. In the example above, there must be a minimum of four licenses on the `compile` **FEATURE** line. If fewer licenses are available, only the first set of reservations (up to the license limit) is used.

If this data were in file `/a/b/sampled/licenses/sampled.opt`, then modify the license file `VENDOR` line as follows:

```
VENDOR sampled /etc/sampled /sample_app/sampled/licenses/sampled.opt
```

Limiting Access for Multiple Users

Each `INCLUDE`, `INCLUDEALL`, `INCLUDE_BORROW`, `INCLUDE_ENTITLEMENT`, `EXCLUDE`, `EXCLUDEALL`, `EXCLUDE_BORROW`, `EXCLUDE_ENTITLEMENT`, `MAX`, and `RESERVE` line must have a single user name (or group) listed. To affect more than one user name create a `GROUP`. For example to exclude bob, howard, and james from using the feature called `toothbrush`, create the following options file:

```
EXCLUDE toothbrush USER bob
EXCLUDE toothbrush USER howard
EXCLUDE toothbrush USER james
```

However, there is an easier way. Create a `GROUP` and exclude the list of users from using the feature. Like the previous example, the following options file excludes bob, howard, and james from using the feature called `toothbrush`:

```
# First define the group "Hackers"
GROUP Hackers bob howard james
# Then exclude the group
EXCLUDE toothbrush GROUP Hackers
```

Now when you want to allow or deny access to any feature to that group, you have an alias list to make it simple.

Use `HOST_GROUP` to allow, deny, or reserve licenses for multiple hosts. For example, to exclude all users logged in on the hosts fred and barney from using a feature called `f1`, add these lines to your options file:

```
HOST_GROUP writers fred barney
EXCLUDE f1 HOST_GROUP writers
```

See Also

[HOST_GROUP](#) for more information about defining groups

EXCLUDE Example

```
#First Define the group "painters"
GROUP painters picasso mondrian klee
EXCLUDE spell GROUP painters
EXCLUDE spell USER bob
EXCLUDE spell INTERNET 123.123.123.*
```

This options file:

- Prevents the users `picasso`, `mondrian`, and `klee` from using the feature `spell` on any system on the network.
- Prevents the user `bob` from using the feature `spell` on any system on the network.
- Prevents any user logged into a host with an IP address in the range `123.123.123.0` through `123.123.123.255` from using the feature `spell`.
- Allows any other user, as long as they are not on the excluded IP addresses, *and* they are not a member of the `painters` `GROUP`, *and* they are not `bob`, to use feature `spell` (by implication).

Note that `bob` could have been added to the group `painters`. However, `painters` might be used for some other purpose in the future so the license administrator chose to handle `bob` as a special case here. In this case, the two `EXCLUDE` statements concatenate to create a list of four users.

EXCLUDE_ENTITLEMENT Example

```
#First Define the group "admin"  
GROUP admin johns adrianp maryt  
EXCLUDE_ENTITLEMENT qf573k GROUP admin  
EXCLUDE_ENTITLEMENT qf573k USER bob  
EXCLUDE_ENTITLEMENT qf573k HOST corde1ia
```

This options file:

- Prevents the users johns, adrianp, and maryt from activating any licenses contained in the fulfillment record obtained using the entitlement Id qf573k on any system on the network.
- Prevents the user bob from activating any licenses contained in the fulfillment record obtained using the entitlement Id qf573k on any system on the network.
- Prevents any user on the system called corde1ia from activating any licenses contained in the fulfillment record obtained using the entitlement Id qf573k.
- By implication allows any other users on any system other than corde1ia to activate the licenses contained in the fulfillment record obtained using the entitlement Id qf573k.

INCLUDE Example

```
INCLUDE paint USER picasso  
INCLUDE paint USER mondrian  
INCLUDE paint HOST bigbrush
```

This options file:

- Allows the user picasso to use the feature paint on any system on the network.
- Allows the user mondrian to use the feature paint on any system on the network.
- Allows any user, as long as they are on the host bigbrush, to use feature paint.
- Denies access to the feature paint to anyone except picasso, mondrian, or anyone from the host bigbrush (by implication).

INCLUDE_ENTITLEMENT Example

```
INCLUDE_ENTITLEMENT gy7210 USER tom  
INCLUDE_ENTITLEMENT gy7210 USER anthony  
INCLUDE_ENTITLEMENT gy7210 HOST jupiter
```

This options file does the following:

- Allows the user tom to activate any licenses contained in the fulfillment record obtained using the entitlement Id gy7210 on any system on the network.
- Allows the user anthony to activate any licenses contained in the fulfillment record obtained using the entitlement Id gy7210 on any system on the network.
- Allows any user, as long as they are on the host jupiter to activate any licenses contained in the fulfillment record obtained using the entitlement Id gy7210.

- By implication, denies the activation of any licenses contained in the fulfillment record obtained using the entitlement Id gy7210 to anyone except tom, anthony, or someone on the host jupiter.

Ensuring License Availability

You can configure multiple license servers to allow FlexEnabled applications to continue to check our licenses if one of the license servers goes down. This failover protection for license servers can be provided using either of the following methods:

- **Redundancy using the license search path:** Configure and maintain multiple independent license servers, each with a subset of the total licenses available to the enterprise. Configure the FlexEnabled client with the license servers in the license search path. This provides load balancing capabilities and limited failover protection. You must manage different versions of the license rights on each license server. This configuration option is available when licenses are held in license files and in trusted storage.
- **Three-server redundancy:** Configure and maintain a set of three license server systems configured specifically for three-server redundancy. This provides failover protection only. You manage only one version of the license file and vendor daemon on all three license servers. This configuration option is only available when licenses are held in license files.

Do not store your license files on a single network file server (separate from the license servers) if you are using either of these methods of failover protection: The failure of the file server will cause all the license servers to fail.

Redundancy Using the License Search Path

In this configuration you install multiple license servers that each use a subset of the available licenses. Network machines are configured with a license search path that contains details of each license server. A FlexEnabled application tries each license server on the license search path in order until it succeeds or gets to the end of the list.

Example of Redundancy Using the License Search Path

This example demonstrates the use of two license servers, **chicago** and **tokyo**, that serve five licenses each for the features **f1** and **f2**. The publisher supplies the following license files:

- **For chicago**

```
SERVER chicago 17007ea8 1700  
VENDOR sampled /etc/mydaemon  
FEATURE f1 sampled 1.000 31-dec-2020 5 SIGN=.....
```

```
FEATURE f2 sampled 1.000 31-dec-2020 5 SIGN=.....
```

- **For tokyo**

```
SERVER tokyo 17007ea8 1700
VENDOR sampled /etc/mydaemon
FEATURE f1 sampled 1.000 31-dec-2020 5 SIGN=.....
FEATURE f2 sampled 1.000 31-dec-2020 5 SIGN=.....
```

The license search path is set on the network machines using the LM_LICENSE_FILE environment variable so that machines in the US request licenses first from the license server **chicago** and machines in Japan request licenses first from the license server **tokyo**.

- **US machines** set LM_LICENSE_FILE to - 1700@chicago:1700@tokyo
- **Japanese machines** set LM_LICENSE_FILE to - 1700@tokyo:1700@chicago

This example uses UNIX syntax (:) for separating entries on the license search path. See [Setting the License Search Path Using an Environment Variable](#) for full details of the license search path syntax.

Limitations of Redundancy Using the License Search Path

The main limitation is that this method only provides limited protection: When a license server fails, the licenses it serves are no longer available.

All licenses must be checked out from a single server

By default, once a FlexEnabled application has successfully checked out a license from a license server, all subsequent license requests from that application must be served by the same license server. When an application makes subsequent license requests and no more licenses are available from that license server, the license request is denied even though licenses may exist on another server. However, this behavior is configurable by software publishers. Contact your software publisher to determine whether or not each new license request scans all the license servers.

Licenses are queued from a single server

If the application supports license queuing, all licenses are queued from the first license server on the list rather than the request moving to another license server.

Overview of Three-Server Redundancy

Using the three-server redundancy capability in FlexNet Publisher, all three license servers operate to form a triad. The license servers send periodic messages to each other to make sure that at least two servers are running and communicating. A quorum is formed when at least two of the three license servers are running and communicating with each other.


The license servers are identified as either primary, secondary, or tertiary. One license server is also designated as the master [m] and is responsible for:

- Serving licenses to FlexEnabled applications
- Recording information into the debug log.
- Recording information into the report log.

If the master fails, then another license server becomes the master.


In the following figure, the primary license server is the master [m]. When a FlexEnabled application sends a checkout request for a license, the master responds and then serves the license to the FlexEnabled application.

Figure 14-1: Three-Server Redundancy Overview



If the master fails, then the secondary license server becomes the master (see the following figure) and will server licenses to FlexEnabled applications. The tertiary license server can never be the master. If both the primary and secondary license servers go down, licenses are no longer served to FlexEnabled applications. The master will not serve licenses unless there are at least two license servers in the triad running and communicating.

Figure 14-2: Three-Server Redundancy Backup Failover



Understanding How License Servers Communicate

When started, each license server reads the license file and checks that it can communicate with the other license servers. Until each license server establishes this first connection with the others, it will continue to send messages periodically.

Once the initial communication has been established, each license server periodically sends a heartbeat to the others. Heartbeats are messages sent over TCP/IP. Each license server sends a heartbeat and waits for a response from the other license servers. If a license server does not receive a response, it shuts down the vendor daemon so that it cannot serve licenses. A publisher or license administrator can configure the amount of time a license server waits to receive a heartbeat using the `HEARTBEAT_INTERVAL` property.

Poor network communication causes system performance to slow. Slow network communication can also cause a delay in the transmission of heartbeats between license servers.

Configuring License Servers for Three-Server Redundancy

Perform the following steps to configure three-server redundancy:

1. Before obtaining the license server software package from the publisher, identify and set up the three systems. When selecting systems, make sure they are stable. Do not use systems that are frequently rebooted or shut down.
2. Send the publisher the hostname and hostid values for these systems. Ask the publisher what system identifier they need for the hostid. This could be an Ethernet address, disk serial number, etc. The publisher will create license server components specifically for these systems.



Note • Best practice is to obtain a hostid of the same type for each of the three machines. Issues can arise if different hostid types are used in the configuration. If you plan to obtain the hostid using the default hostid type for a given machine, be aware that the default type can vary between operating-system platforms.

3. After receiving the license server package from the publisher, change the following `SERVER` line properties in the license file if necessary:
 - **port number** the license servers uses to listen for communication
 - **PRIMARY_IS_MASTER** keyword
 - **HEARTBEAT_INTERVAL** property

Do not change the hostid values. If the hostid changes at any time, the license administrator must work with the software publisher to obtain a new license file.

4. Perform any additional configuration as required by the software publisher.
5. Copy or install the license server software package to each of the three systems.
6. Start the license servers in the following order: primary, secondary, and then tertiary.

An Example License File

The following is an example of a license file that is configured for three-server redundancy.

```
SERVER pat 17003456 2837 PRIMARY_IS_MASTER
SERVER lee 17004355 2837
SERVER terry 17007ea8 2837
VENDOR demo
FEATURE f1 demo 1.0 31-dec-2020 10 SIGN="<...>"
```

```
FEATURE f2 demo 1.0 31-dec-2020 10 SIGN="<...>"
```

The following portions of the license file directly affect the three-server redundant configuration:

- **SERVER** lines—Each line contains this information for the given server:
 - The **host name** value: **pat**, **lee**, or **terry**.
 - The **hostid** value: **17003456**, **17004355**, or **17007ea8**. This example uses the value returned by the `lmhostid` utility default `hostid` type for each server.



Note • Keep in mind that the default `hostid` type can vary between operating-system platforms. Best practice is to use the same `hostid` type for all three servers.

- The TCP/IP **port**—In this example, **2837**. All servers use the same port to listen for communication.

The following properties of the license file do not affect the three-server redundant configuration directly, but are used to define license rights or configure the license server.

- **VENDOR** line—This required element references the publisher's vendor daemon.
- **FEATURE** lines—The two features, `f1` and `f2`, define the license rights. The `SIGN` value for each **FEATURE** line encodes the license server `hostid` values.

Managing License Servers in a Three-Server Redundant Configuration

Using the `lmstat` Utility

The output message generated by the `lmstat` utility identifies which license server is the master. In the following example `lmstat` output, the secondary license server is the master.

```
[Detecting lmgrd processes...]  
License server status: 30000@RMD-PRIMARY,30000@RMD-SECONDARY,  
30000@RMD-TERTIARY  
License file(s) on RMD-PRIMARY: C:\server\3.lic:  
RMD-PRIMARY: license server UP v11.4  
RMD-SECONDARY: license server UP (MASTER) v11.4  
RMD-TERTIARY: license server UP v11.4
```

Starting and Stopping License Servers

To start the entire system, you must start each license server manager (`lmadmin` or `lmgrd`). Generally, it is good practice to start the primary license server before the secondary or tertiary license server. This allows the primary license server to become the master before the others start. If you start the secondary and tertiary before the primary, then the secondary will establish itself as master.

If you do not set the `PRIMARY_IS_MASTER` keyword for the primary license server, then the order in which you start the license servers is important. If you do not set this property, when you start the primary license server after the secondary license server control will not transfer to the primary license server. By setting the `PRIMARY_IS_MASTER` keyword, you ensure that when the primary license server is running, it is always the master.

In three-server scenarios, a system administrator may wish to shut down one of the servers to perform maintenance on it, while the other two servers maintain a quorum and continue to serve licenses. Previously, shutting down a license server in a triad through `lmdown` (or `lmtool`s) would shut down the entire triad. Now, a system admin can run **`lmdown -c 3server-license.lic`** from one of the machines in the triad. `lmdown` will read the 3-server license file and provide a prompt asking which of the three listed servers to shut down.

Running the License Server Manager as a Service on Windows

There are no dependencies or known issues related to running the license server manager as a service in this configuration.

Logging and the Debug Log

When using three-server redundancy, the master records information to its local debug log and report log (and the Windows event log if this is configured). If this system fails, another license server becomes the master and records information to its local debug log and report log. Subsequently, there may be different versions of the debug log and report log on the primary and secondary license server which each contains different information.

Using Other Capabilities with Three-Server Redundancy

The following section describe other capabilities available in FlexNet Publisher and how they interact with three-server redundancy.

Configuring the License Search Path

This configuration can be performed by either the software publisher or the license administrator. Before a FlexEnabled application can check out a license, it must know where to locate the license rights. The license search path identifies the location of license rights.

When connecting to a license server configured for three-server redundancy, the FlexEnabled application must use the `<port>@<host>` convention (and not a license file location) in the license search path.

The license search path should list the license servers in the same order that they appear in the license file. This helps shorten the amount of time it takes to identify the master server and respond to the checkout request. Although the configuration will work if you include only one of the license servers in the license search path, this may lengthen the amount of time it takes for the license server to respond to the checkout request. This is because the license server must identify all other license servers and designate a master.

Separate each `<port>@<host>` entry with a comma. Using the previous license file as an example, the license search path should be the following:

`2837@pat,2837@lee,2837@terry`

The FlexEnabled application will try to connect to each of the license servers in the list, in the order listed, until it either successfully connects to a license server or reaches the end of the list. This helps ensure that the FlexEnabled application can connect to the quorum.

Specifying Three-Server Redundancy in the License Finder

When the license search path has not been configured, the FLEXlm License Finder dialog is displayed on Windows platforms when a FlexEnabled application is run.



Task

To specify a triad of license servers in the License Finder dialog:

1. Select **Specify the License File**.
2. Click **Next**.
3. Type the path name or use the browse button to specify your three-server redundant license file. [An Example License File](#) shows a typical three-server redundant license file.
4. Click **Next**.

Note that the License Finder dialog option, **Specify the License Server System**, allows you to only specify a single license server and not a triad of license servers.

Using License File Keywords

The following keywords and properties for the **SERVER** line allow you to modify the configuration.

- **Host:** this is the hostname of the system. The publisher should know this information when generating the license file. This value can be changed after the license file has been signed.
- **Port:** the port number that the license server uses to listen for communication. Unlike single license servers, each SERVER line must include a port number. This can be any number in the range 0 to 65535 that is not used by another process running on the system. This value can be changed after the license file has been signed. If you are using `lmadmin`, you do not need to edit the license file; you can configure the port number using the interface. See the online help for more details.

To make it easier to administer the license server, we strongly recommended that you define the same port number for each SERVER line. This value can be changed after the license file has been signed.

- **PRIMARY_IS_MASTER:** this keyword ensures that the primary server is the master whenever it is running and communicating with one of the other license servers.
 - If this is set and the primary server goes down, when the primary server comes back up again, it will always become the master.
 - If this is not set and the primary server goes down, the secondary server becomes the master and remains the master even when the primary server comes back up. The primary can only become the master again when the secondary license server fails.

This parameter is optional and should be placed on the first SERVER line. This value can be changed after the license file has been signed. The license server must be running a version 10.8 or later vendor daemon to use this keyword.

- **HEARTBEAT_INTERVAL=seconds:** this indicates how long the license servers wait to receive a heartbeat from another license server before shutting down the vendor daemon. This value is used in the following equation to calculate the actual timeout value:

$$\text{timeout} = (3 * \text{seconds}) + (\text{seconds} - 1)$$

The default value is 20, which equates to an actual timeout of 79 seconds. Valid values are 0 through 120. This parameter is optional and should be placed on the first SERVER line in the license file. This value can be changed after the license file has been signed. The license server must be running a version 10.8 or later vendor daemon to use this keyword.

Using Options File Keywords

None of the keywords in the options file affect three-server redundancy.

Troubleshooting Tips and Limitations for Three-Server Redundancy



Important • Three-server redundancy configurations require all three servers use the same platform type. You can use any of the following platform types in the configuration, but each server must use the same platform type: VM_* or PHY_*.

Separating the Contents of a License File

Because the hostid values in the SERVER lines are computed into the signature of each feature definition line, make sure you keep SERVER lines together with any feature definition lines as they were generated. This means that if you move a feature definition line to another file, you must also move the respective SERVER lines and VENDOR line.

Putting the License File on a Network File Server

Do not put the license file on a network file server. If you do this, you lose the advantages of having failover protection because the file server becomes a possible single point of failure.

Using License Servers in Heavy Network Traffic

On a network with excessive traffic, the license servers may miss heartbeats which causes them to shut down the vendor daemon. The master may then stop serving licenses. If you find that heavy network traffic causes this to occur, you should set the HEARTBEAT_INTERVAL to a larger value. Enterprises can experience a performance issue when there is slow network communication or if FlexEnabled clients are using a dial-up link to connect to the network.

Using Multiple Vendor Daemons

The license server manager (lmadmin or lmgrd) can not start vendor daemons from multiple software publishers when configured for three-server redundancy. The license server manager can only manage one vendor daemon. If one of the systems runs more than one vendor daemon, then the license administrator must run separate instances of the license server on that system to support the other vendor daemons. Make sure that the port numbers do not clash.

Switching Between Three-Server Redundancy and Single-Server Configuration

While running, the license server manager (`lmadmin` or `lmgrd`) is not designed for switching from three-server redundancy to a single-server configuration (and vice-versa). To switch configurations, you need to do the following:

1. Shut down the license server manager in the single-server configuration or, in a three-server redundancy, all the license server managers currently running.
2. Do one of the following:

- For `lmadmin`:

- a. From the `lmadmin` installation directory on a given machine, import the required license files for the new configuration to which you are switching (either the three-server-redundant or single-server configuration):

```
lmadmin -import <new_license_file_list> -force
```

- b. Restart `lmadmin`.

- For `lmgrd`:

To restart `lmgrd` on a given machine in the configuration to which you are switching (either the three-server-redundant or single-server configuration), enter the following from the directory in which `lmgrd` is located:

```
lmgrd -c <new_license_file_list>
```

Avoiding Undefined `lmdown` Behavior

If any two license servers in a three-server redundancy group are started with the `-allowStopServer no` option (`lmadmin`) or the `-x lmdown` option (`lmgrd`), then the behavior of `lmdown` is undefined for that system.

Managing Virtualized License Servers for File-Based Licensing

Virtualization software allows you to run multiple instances of a license server on a single machine. You can use virtualized license servers to take advantage of the high availability and fault tolerance that virtual machines offer.



Note • This chapter deals with managing license servers configured for license file-based licensing in a virtual environment. For information about trusted storage-based licensing in a virtual environment, see [Chapter 2, “Trusted Storage.”](#)

Binding Solutions in a Virtual Environment

For license file-based licensing, a license server can be bound to one of:

- the UUID of the virtual machine (refer VM_UUID)
- the MAC address of the virtual machine (ETHER)
- A FLEXID, where the hypervisor concerned supports USB passthrough of the dongle

Setting Up a Virtual License Server on Microsoft Hyper-V

The process of setting up a license server on a virtual machine hosted by a Microsoft Hyper-V hypervisor depends on the hostid chosen to bind the license file to the license server. This hostid can be either the virtual machine's UUID (Universally Unique ID) or the hostid of a physical machine--either the hypervisor or a remote physical machine that communicates with the virtual machine. The following sections demonstrate these two binding methods.

Using the UUID Hostid

In general, the process for binding to the UUID of the virtual machine hosting the license server follows this outline.

**Task****To bind to the UUID of the virtual machine hosting the license server**

1. Identify the virtual machine on which the license server will be run.
2. Run the following command from the command line of the virtual machine:
lmhostid -ptype VM -uuid
3. Send the output of this command to the software publisher. The software publisher sends back a license certificate in which the license server is bound to the UUID value.
4. Modify the license certificate to configure server parameters (like TCP port number, options file, or other parameters).
5. Launch the license server on the virtual machine by pointing to the license certificate.



Note • If the license server has to be moved to another physical machine, simply copy the virtual-machine image and move it to the new physical host machine.

Setting Up a Virtual License Server on VMware ESXi or XenServer

The process of setting up a license server on a virtual machine hosted by a VMware ESXi or XenServer hypervisor depends on the hostid chosen to bind the license file to the license server. This hostid can be either the virtual machine's UUID (Universally Unique ID) or the hostid of a remote physical machine that communicates with the virtual machine. The following sections demonstrate these two binding methods.

If your license-server virtual machine is being hosted by a VMware ESX hypervisor.

Using the UUID Hostid

In general, the process for binding to the UUID of the virtual machine hosting the license server follows this outline.

**Task****To bind to the UUID of the virtual machine hosting the license server**

1. Identify the virtual machine on which the license server will be run, and download the platform-specific `lmhostid` utility from the Flexera Software website onto this virtual machine.
2. Run the following command from the command line of the virtual machine:
lmhostid -ptype VM -uuid
3. Send the output of this command to the software publisher. The software publisher sends back a license certificate in which the license server is bound to the UUID value.
4. Modify the license certificate to configure server parameters (like TCP port number, options file, or other parameters).

5. Launch the license server on the virtual machine by pointing to the license certificate.



Note • If the license server has to be moved to another physical machine, simply copy the virtual-machine image and move it to the new physical host machine.


Additional Considerations

Consider the following when configuring the binding agent:

-
- **Hypervisor COS use**--Running a license server or a FlexEnabled client application on the COS of the hypervisor is not supported. The license server and FlexEnabled client application must run either on a physical machine or on a virtual machine.

Virtualization Support

The following picture illustrates how the FlexNet licensing server or a FlexEnabled application operates within a Virtualization stack. The table below the picture lists the Virtualization stacks that FlexNet Publisher supports.



Use the table available in Release notes to determine the supported Virtualization stacks.

Licensing in a Cloud-Computing Environment

This chapter provides the following information to help the license administrator implement secure software licensing in a cloud-computing:

- [Licensing Challenges in a Cloud Environment](#)
- [Scope of Support for Cloud Licensing](#)
- [Use Cases for Licensing Software in the Cloud](#)
- [Hostids for Binding](#)



Note • For simplification, the remainder of this chapter refers to the cloud-computing environment as the cloud environment.

Licensing Challenges in a Cloud Environment

The fundamental concept of software licensing involves binding the license to characteristics of the physical machine on which the software resides and, for served licenses, on which the license server resides. These characteristics, called *binding elements*, include machine identities such as the Ethernet address or the host name. However, a cloud environment runs on virtual machines that are instantiated and brought down frequently. Consequently, the traditional hardware-based binding elements are not reliable in a cloud environment. Additionally, the FlexNet Publisher bare-metal-bindings (BMB) feature available in prior releases for on-premises virtual machines is unusable in a cloud environment; the license administrator does not have access to the physical hardware on which the virtual instances are running. This access is a prerequisite for the BMB feature.

A public cloud provider charges the customer based on the number of hours a machine instance is used. To optimize billing charges, a user typically stops or terminates an instance when it is not in use. This type of stop-restart usage is contrary to the on-premises machine usage, which is typically continuous. Therefore, the ideal binding element in the cloud environment is one that has these attributes:

- Globally unique within the cloud infrastructure to prevent over-licensing by cloned images

- Unchanging between normal start/stop, suspend/resume, live-process migration, and reboots of machine instances
- Not easily changed by the user
- Not usable when the license is outside the cloud

FlexNet Publisher provides licensing solutions that meet these binding-element requirements. These solutions are based on typical licensing use cases in a cloud environment and are within the scope of cloud-licensing support for this release.

Scope of Support for Cloud Licensing

In this release, FlexNet Publisher limits its initial support for cloud licensing to the following:

- Licensing in the Amazon EC2 environment only
- Certificate-based licensing only
- 32-bit Windows, 64-bit Windows, 32-bit Linux, or 64-bit Linux machine instances (all in IPv4 format) for running FlexEnabled applications and license servers

Additionally, FlexNet Publisher does *not* support the following for cloud licensing:

- Cross-version signatures on served, node-locked license clients
- Composite hostids using Amazon machine bindings
- Three-server redundancy



Note • *Cloud environments have other methods that compensate for three-server redundancy to ensure high availability of the license server.*

Use Cases for Licensing Software in the Cloud

The following use cases describe typical licensing scenarios in a cloud environment. For each case, FlexNet Publisher provides a binding-element solution specific to the Amazon EC2 environment.



Note • *The machine instance referenced in these use cases is known as the AMI (Amazon Machine Image) instance in the Amazon EC2 environment.*

Case 1: Traditional Served and Unserved Licensing in a Public Cloud

This use case involves software users (end-users or license administrators) deploying FlexEnabled applications in a public cloud much like deploying these applications on user premises. In the case of served licenses, the user can deploy and bind the FlexNet Publisher license server to a machine instance in the cloud. The user then deploys the

FlexEnabled application as a license client to machines instances in the cloud, to machines in the enterprise network, or to both, with all clients pointing to the license server in the cloud. In the case of unserved licenses, the user simply deploys the node-locked FlexEnabled application to one or more machine instances in the cloud.

Binding Elements Required for Case 1

In the Amazon EC2 environment, this use case involves binding licenses to the AMI instance on which the license server resides or, for any node-locked licenses, to the AMI instance on which the specific license client resides. The required binding elements include the following:

- For served licenses, the **Internet address** for the AMI instance on which the server resides
- For node-locked licenses (served or unserved), the **AMI UUID** for the AMI instance containing the license client

For a description of these binding elements and how to obtain them, see the [Hostids for Binding](#) section.

License Administrator Tasks for Case 1

Perform the following basic tasks for traditional served and unserved licensing in the cloud:

1. Open an Amazon Web Services account to use Amazon EC2.
2. Depending on the use case, set up a separate AMI instance for each license client and for the license server.



Note • *A large-sized AMI instance is recommended for the license server.*

3. On the AMI instance for the license server, perform the following additional tasks:
 - Ensure that the ports for the license server, vendor daemon, and the webport (for the license server manager user interface) allow incoming connections.
 - Set the appropriate EC2 security group to control access to the license server port.
 - Associate an Internet address with the AMI instance.
4. Download the platform-specific `lmhostid` utility from the Flexera Software website to these locations:
 - For served licenses, the AMI instance hosting the license server
 - For node-locked licenses, each license-client AMI instance to which you intend to bind licenses
5. To obtain the required hostids listed in [Binding Elements Required for Case 1](#), run the appropriate `lmhostid` command on the AMI instances.
See [Hostids for Binding](#) for more information about the different `lmhostid` commands.
6. Send the hostids to the software publisher, who then uses this information to generate the license certificate.
7. When you receive the license file from the publisher, modify the license certificate to configure server parameters (like TCP port number, options file, or other parameters.)
8. Install the required FlexEnabled components on the AMI instances, using methods similar to on-premises deployment.

Case 2: Traditional Served and Unserved Licensing in a Virtual Private Cloud

A virtual private cloud (VPC) is a portion of the public cloud that forms the private cloud for a specific corporate enterprise. The enterprise deploys all of its network security policies on this VPC by establishing a secure tunneling mechanism (a virtual private network, or VPN) between the corporate network and the cloud components. This model is popular with enterprises who are concerned about security issues associated with the public cloud. Cloud providers, such as Amazon EC2, typically charge for both VPC machine-instance usage and for data crossing the VPN tunnel. Amazon recommends using the Elastic Network Interface (ENI) for VPC licensing.

Binding Elements Required for Case 2

The Mac address of the Amazon Elastic Network Interface (ENI), can be extracted in an Amazon instance through the pre-existing ETHER keyword.

License Administrator Tasks for Case 2

Perform the following basic tasks for traditional served and unserved licensing in a virtual private cloud:

1. Set up a separate AMI instance for each license client and for the license server.



Note • A large-sized AMI instance is recommended for the license server.

2. On the AMI instance for the license server, perform the following additional tasks:
 - Ensure that the ports for the license server, vendor daemon, and the webport (for the license server manager user interface) allow incoming connections.
 - Set the appropriate EC2 security group to control access to the license server port.
3. Download the platform-specific `lmhostid` utility from the Flexera Software website to these locations:
 - For any served node-locked licenses, each license-client AMI instance to which you intend to bind licenses
4. To obtain the hostids listed in [Binding Elements Required for Case 2](#), run the appropriate `lmhostid` command on the AMI instances.
See [Hostids for Binding](#) for information about the different `lmhostid` commands.
5. Send the hostids to the software publisher, who then uses this information to generate the license certificate.
6. When you receive the license file from the publisher, modify the license certificate to configure server parameters (like TCP port number, options file, or other parameters.)
7. Install the required FlexEnabled components on the AMI instances, using methods similar to on-premises deployment.

For served licenses, continue with these steps:

8. Launch the license server on the virtual machine by pointing to the license certificate.

Hostids for Binding

The binding element used to bind a license to the specific AMI instance on which the license client or the license server resides is called the *hostid* of the AMI instance. This section discusses the types of hostids that FlexNet Publisher supports for licensing in the Amazon EC2 environment.

Supported Hostid Types

The following table describes the hostids that FlexNet Publisher supports in the Amazon EC2 environment. For instructions on how to retrieve each hostid, see the next section, [Retrieving and Specifying Hostids](#).

Table 16-1 • Hostid Types Supported in Amazon EC2

Hostid Type	Binding Applicability	Characteristics
Elastic IP (EIP) address (AMZN_EIP)	License Server only	<ul style="list-style-type: none"> • IPv4 format only. • For use on the SERVER line in the license file. • Manually assigned to any running AMI instance. • Static identity—that is, can be reassigned to another AMI instance if the current instance crashes. For example, if the instance containing the license server crashes, the license administrator can copy the server to another instance and reassign the IP address. • Cross-version signatures not required. • Specific to Case 1: Traditional Served and Unserved Licensing in a Public Cloud. • The FlexNet Licensing Service must be running to access this hostid.

Table 16-1 • Hostid Types Supported in Amazon EC2

Hostid Type	Binding Applicability	Characteristics
AMI instance UUID (VM_UUID)	License Server only	<ul style="list-style-type: none"> • Unique ID automatically assigned to an AMI instance. • Remains in tact when the instance is suspended, resumed, or rebooted, but disappears if the instance terminates accidentally or crashes. • Cross-version signatures not supported. Therefore, legacy FlexEnabled applications cannot obtain licenses that are bound to this hostid. • Specific to Case 1: Traditional Served and Unserved Licensing in a Public Cloud and Case 2: Traditional Served and Unserved Licensing in a Virtual Private Cloud.
Elastic Network Interface (ENI)	License server only	<ul style="list-style-type: none"> • Extracted through the ETHER keyword.

Retrieving and Specifying Hostids

The following table lists the methods used by the software user or publisher (depending on the use case) to retrieve hostids in the Amazon EC2 environment. The table also shows how a given hostid is used in the license file.



Note • The System Info page in the lmadm user interface does not show these hostids specific to the Amazon EC2 environment. To obtain these hostids, you must use the methods described the following table

Table 16-2 • Retrieving and Specifying Hostids

Hostid Type	Method to Obtain ID	License File Syntax
Elastic IP (EIP) address (AMZN_EIP)	<p>Use either method:</p> <ul style="list-style-type: none"> On the AMI instance containing the server, run the following command: <code>lmhostid -ptype AMZN -eip</code> Obtain the EIP from the Amazon infrastructure. <p><i>This lmhostid command actually returns the public IP address for the AMI instance, and this value might not always be the EIP address. Consider the following:</i></p> <ul style="list-style-type: none"> If the AMI instance is associated with an EIP address, the EIP address is the public IP address. Consequently, lmhostid returns the EIP address. If the AMI instance has no EIP address associated with it, EC2 assigns a default public IP address, which is the value that lmhostid returns. <p><i>FlexNet Publisher strongly recommends obtaining the EIP address. To ensure lmhostid returns this value, associate the instance with an EIP address before running the command. If necessary, consult Amazon for help with this process.</i></p>	<p>Syntax:</p> <p><code>AMZN_EIP=IPv4 address</code></p> <p>Example:</p> <p><code>SERVER this_host AMZN_EIP=184.72.45.35</code></p>
VM_UUID (AMI instance IID)	<p>Use either method:</p> <ul style="list-style-type: none"> On the AMI instance containing the license server, run the following command: <code>lmhostid -ptype VM -uuid</code> Obtain the instance ID from the Amazon infrastructure. 	<p>Syntax:</p> <p><code>VM_UUID=universal unique identifier for AMI Instance ID</code></p> <p>Example:</p> <p><code>HOSTID=VM_UUID=i-7d4d09db1</code></p>



Note • The FlexNet Licensing Service must be running to access this hostid.

17

IPv6 Support

Internet Protocol version 6 (IPv6) is the next generation IP protocol. This section contains information for software publishers who want to support IPv6 addresses in their license model. The information in this section assumes the reader has a familiarity with the IPv6 networking protocols.

The following sections of this chapter describe the FlexNet Publisher support for IPv6 and contains information related to both license file-based licensing and trusted storage-based licensing.

- [Capabilities that Support IPv6](#)
- [Testing Considerations](#)

Capabilities that Support IPv6

This section describes the capabilities in FlexNet Publisher that support IPv6. It includes information about both license file-based licensing and trusted storage-based licensing.

When working with a software publisher to obtain a software package that supports IPv6, you should collect and provide the IP addresses of systems (FlexEnabled clients and license servers) that will be used in the license file.



Note •

- *In the license and options files, FlexNet Publisher supports only the site-local form of the IPv6 address (those addresses prefixed with FEC0).*
- *While an IPv6 address can be used in license or options files, the best-practice recommendation is to use hostname or IPv4 address.*
- *A mix of IPv4 and IPv6 addresses in the license and/or options file is not supported.*

License File

In a license file, the SERVER line can define an IPv6 address as the hostid and host value.

In FEATURE, INCREMENT, and UPGRADE lines, an IPv6 address can be used as the HOSTID value when using the INTERNET type.

The following keywords (used with duplicate grouping) support IPv6 addresses:

- The DUP_GROUP keyword, using HOST as the type.
- The SUITE_DUP_GROUP keyword using HOST as the type.

Options File

An options file can contain an IPv6 address to specify host restrictions when using the:

- INTERNET type in these keywords: EXCLUDE, EXCLUDEALL, EXCLUDE_BORROW, INCLUDE, INCLUDEALL, INCLUDE_BORROW, MAX, and RESERVE.
- HOST type in these keywords: EXCLUDE, EXCLUDE_ENTITLEMENT, EXCLUDEALL, EXCLUDE_BORROW, INCLUDE, INCLUDE_ENTITLEMENT, INCLUDEALL, INCLUDE_BORROW, MAX, and RESERVE
- HOST_GROUP keyword (it takes IP addresses).

License Search Path

Entries in the license search path that use the 'port@host' convention to identify the license server, can specify an IPv6 address as the 'host' value.

FlexEnabled Application

Entries in the license search path that use the *port@host* convention to identify the license server, can specify an IPv6 address as the *host* value.

- **flxActCommonHandleSetRemoteServer(...)**
- **flxActBorrowReturn(...)**
- **flxActBorrowActivate(...)**

The following attributes, set using the **lc_set_attr** function, support IPv6 addresses:

- LM_A_HOST_OVERRIDE
- LM_A_PROMPT_FOR_FILE (Windows Only) - the dialog that appears takes an IPv6 address.
- LM_A_DISPLAY_OVERRIDE
- LM_A_INTERNET_OVERRIDE

You can use an IPv6 address when setting the LM_DUP_HOST flag in the **lc_checkout** function.

License Server

The **lmhostid** utility returns an IPv6 address.

Environment Variables

Listed below are the environment variables that handle performance and hostname resolutions.

FNP_IP_ENV

This client-side environment variable determines how the client's IP address is presented to the server.

- If the variable is set to a value of 0, 4, or 6, the IP address sent to the server is resolved on the client, from the client's hostname, as follows:
 - If the variable is set to 0, then the client resolves its hostname to both an IPv4 and an IPv6 address.
 - If the variable is set to 4, then the client resolves its hostname only to an IPv4 address.
 - If the variable is set to 6, then the client resolves its hostname only to an IPv6 address.
- If the variable is set to 1 (default value), the client-side hostname resolution is bypassed. Instead, the client's IP address is determined from the socket connection at the server, which means that a NAT-translated IP address for the client can be obtained.

FNP_IP_PRIORITY

The environment variable FNP_IP_PRIORITY decides the IP priority for hostname resolution, and can apply to the server, the client, or utilities like `lmhostid`. Values are:

- **4** (default): hostname resolution is attempted to IPv4 address first; if that fails, resolution to IPv6 address is attempted.
- **6**: hostname resolution is attempted to IPv6 address first; if that fails, resolution to IPv4 address is attempted.

Examples of when to set to this value:

- on the machine where running `lmhostid`, if IPv6 address is required from `lmhostid -internet`
- on the client if node-locked IPv6 INTERNET HostID is used
- on the server if IPv6 address is used in the options file or as a server HostID.

Note: IPv4 and IPv6 addresses cannot be mixed on the server.

Client IP Address Received by the Server

Clients send both IPv4 and IPv6 addresses in the checkout message to the server.

In some licensing models, it may be desirable for the server to operate on a NAT-translated IP address instead of the client's actual IP address—for example, if using the EXCLUDE keyword in an options file to exclude all clients originating from behind a specific firewall. To enable such use cases, set `FNP_IP_ENV=1` on the client. Setting this environment variable prevents the client resolving its own hostname to an IP address, which means the server instead obtains an IP address for the client from the socket connection.

Using Wildcards in an IPv6 Address

The wildcard character, "*", may be used in place of an entire field or on a byte-by-byte basis to specify a range of addresses without having to list them all. For example, in this example feature definition line is locked to four specific addresses:

```
FEATURE f1 myvendor 1.0 31-dec-2020 uncounted \
  HOSTID="INTERNET=127.17.0.1,\
  INTERNET=fec0::1:e947:a213:1378:253c,\
  INTERNET=127.17.0.4,\
  INTERNET=fec0::1:e947:a213:1378:253c" \
  SIGN=0
```

In the following example feature definition line specifies an entire range of addresses, including the four specific ones from the line above:

```
FEATURE f1 myvendor 1.0 31-dec-2020 uncounted \
```

```
HOSTID="INTERNET=127.17.0.*,\  
INTERNET=fec0:0db8:0000:0000:*:*:*:000*"\  
SIGN=0
```

Testing Considerations

When testing IPv6-compatible FlexEnabled applications and license server, remember to accommodate for the behavior of 4to6 routers, 6to4 routers, and IPv6 firewalls configured on your system.

Managing Licenses from Multiple Software Publishers

Overview of Multiple License Management Strategies

When you are running FlexEnabled applications from multiple software publishers, you might need to take steps to prevent conflicts during installation. There are several strategies to accomplish this, three of which are presented here:


- Multiple systems, each running one license server manager, one vendor daemon, and using one or more license files.
- One system running multiple license server managers, each managing one vendor daemon and one or more license files.
- One system running one license server manager, that manages multiple vendor daemons, each using its own license files. License files share a common directory.

Each of these three strategies is described in detail in the following sections. Variations are mentioned in [Additional Considerations](#).

Multiple Systems

In this scenario, each license server instance (ladmin or lmgrd, vendor daemon, license file, and other files) is located on a separate system. Each system serves licenses just for its vendor daemon and runs its own local copy of the license server manager. Figure 18-1 shows this arrangement.

Figure 18-1: Multiple License Server Systems



Advantages

- The license files for each software publisher are independent from one another.
- Systems are maintained separately. If one system goes down, the other systems continue to serve licenses for their software publishers.
- Each server has its own debug log.
- The license requests are distributed.

Disadvantages

- Administrative overhead is the highest.

Starting the License Servers

In this configuration, you start the license server on each machine separately. Each server runs a single vendor daemon. Use ladmin or lmgrd as the license server manager.

Using lmadmin

When using `lmadmin`, you can start each license server using the `lmadmin` user interface or a command line. Repeat the procedure on each machine to start the license server on that machine.

Starting the License Servers Using the User Interface



Task *To use the `lmadmin` user interface to start the license servers:*

1. At a command prompt from the **lmadmin** installation directory on the machine, enter `lmadmin`. No special command-line options are required.
2. Open the `lmadmin` user interface. For instructions, see [Accessing the License Server Management Interface in Chapter 9, “License Server Manager “lmadmin.”](#)
3. From the `lmadmin` user interface’s main window, click **Administration** to open the Administration page, and sign in with your administrator credentials.
4. Go to the Vendor Daemon Configuration tab.
5. Click **Import License File**.
6. Select and import the license file.



Note • A status message displayed on the `lmadmin` user interface lists any follow-up steps you need to perform after the import. If the message requests that you start (or restart) the vendor daemon, click **Administer** for the specific vendor daemon on the Vendor Daemon Configuration tab; and then click **Stop** or **Start**.

7. Repeat the import process for each license file you want to import for this server.
8. Close down the `lmadmin` user interface.
9. Repeat the previous steps to start the license server on the next machine.

Starting the License Servers Using the Command Line



Task *To use the command line to start the license servers:*

1. Open a command window on the machine.
2. At a command prompt from the **lmadmin** installation directory, enter the following to import the license files:

```
lmadmin -import <server_system_n_license_list>
```

where `<server_system_n_license_list>` is the list of license files for the specific vendor daemon on the license server, as described in [Managing Multiple License Files](#).



Note • Use the `-force` option along with `-import` if you wish to reset configuration in `server.conf` to the current vendor daemon being imported.

3. Enter **lmadmin** (and any `lmadmin` options you might need) to start the license server. For a description of options, see [lmadmin Command-line Arguments](#) in Chapter 9, “License Server Manager “lmadmin.””
4. Repeat the previous steps to start the license server on the next machine.

Using lmgrd



Task **To start the license server on each machine:**

On each machine, enter the following command:


```
lmgrd -c <server_system_n_license_list>
```

where `<server_system_n_license_list>` is the list of license files for the specific vendor daemon on the license server, as described in [Managing Multiple License Files](#). In turn, the `lmgrd` instance on the machine starts the vendor daemon referred to in its license files.

One System with Multiple License Server Instances

In this model, each vendor daemon and its associated license file or files is served by its own license server manager, and everything is contained in one system. [Figure 18-2](#) depicts this scheme.

Figure 18-2: Multiple license server managers, Multiple License Files



When maintaining separate license servers on the same system, keep in mind:

- If the TCP/IP port number is specified on the `SERVER` line, it must be different for each license server instance. Use a standard text editor to change the TCP/IP port number in each license file so that they are all different. If

you are running 10 instances or less, you can omit all port numbers to let `lmadmin` (or `lmgrd`) assign unique ones for you within the default range of 27000–27009.



Note • For security purposes, best practice is not to let the license server manager assign a default port for each license server. Instead, for each server, specify a unique port number outside of the range 27000 through 27009.

- You must make sure that you are using a compatible version of `lmadmin` (or `lmgrd`) for each particular license file. This is done by using an explicit path. See [Version Component Compatibility](#).
- The number of license server instances is limited only by the CPU, available memory, and networking of the system.

Advantages

- The license files for each software publisher are independent from one another.
- License servers are maintained separately. If one server goes down, the other servers continue to serve licenses.
- Each server has its own debug log.

Disadvantages

- Administrative overhead is high.
- If the system goes down, all licenses are disabled.
- License request load is concentrated to one system.

Starting the License Servers

In this configuration, you start multiple license servers on one machine, each server running a single vendor daemon. Use `lmadmin` or `lmgrd` as the license server manager.

Using lmadmin

To start multiple `lmadmin` instances on the same machine, use the command line.



Important • While you can run multiple `lmadmin` instances on a single machine, best practice is to run multiple vendor daemons with a single instance of `lmadmin`. See [One System with One License Server and Multiple License Files](#).



Task **To start the license server instances on one machine:**

1. Open a command window on the machine.
2. At a command prompt from the directory where the first `lmadmin` is installed, enter the following to import the license files:

```
lmadmin -import <server_system_n_license_list>
```

where `<server_system_n_license_list>` is the list of license files for the specific vendor daemon on the license server, as described in [Managing Multiple License Files](#).

3. To start the `lmadmin` instance, enter the following:

```
lmadmin -webPort <httpPort> -webSecurePort <httpsPort>
```

where:

- `<httpPort>` is the TCP/IP port number that the web server uses to listen for communication with clients connecting to the `lmadmin` user interface. While 8090 is the default port number for the web server, you must provide a different port number for each `lmadmin` instance you are configuring.
- `<httpsPort>` is the TCP/IP port number for the Secure Web Server. You must provide a different port number for each `lmadmin` instance you are configuring.



Important • Specify the `-webSecurePort` option only if you are configuring an HTTP-over-SSL (HTTPS) communication with the `lmadmin` web server interface. To define additional certificate information for the Secure Web Server, access the `lmadmin` user interface using the correct URL based on `<httpPort>`. (On the Administration page, go to the **Secure Web Server** section of the Server Configuration tab.) For more instructions, see [Accessing the License Server Management Interface](#) in Chapter 9, “License Server Manager “lmadmin”.”

You can also specify any other `lmadmin` options you might need to start the license server. For a description of options, see [lmadmin Command-line Arguments](#) in Chapter 9, “License Server Manager “lmadmin”.”

4. Repeat the previous steps to start each `lmadmin` instance on the machine.

Using lmgrd



Task **To start the license servers:**

On the machine, invoke each license server:


- For Server 1: **lmgrd -c vendor_ABC_license_dir_list**
- For Server 2: **lmgrd -c vendor_DEF_license_dir_list**
- For Server 3: **lmgrd -c vendor_XYZ_license_dir_list**

where `vendor_nnn_license_list` is a list of license files as described in [Managing Multiple License Files](#). Each `lmgrd` starts the vendor daemon referred to in its license files.

One System with One License Server and Multiple License Files

In this scenario, one license server manager runs on the system and serves one or more vendor daemons, each with one or more license files. If you are using `lmadmin`, you can maintain license files from different publishers in separate directories. If you are using `lmgrd`, all the license files are usually held in the same directory. The standard filename extension for license files is `.lic`. The number of vendor daemons is not limited by FlexNet Publisher. [Figure 18-3](#) illustrates this scenario.

Figure 18-3: One license server manager, Multiple License Files



Advantages

- The license files can be maintained separately.
- Reduced administrative overhead.

Disadvantages

- One license server manager serves all vendor daemons. If the license server manager goes down, all licenses are unavailable.
- If the system goes down, all licenses are unavailable.
- Output from all vendor daemons goes into one common debug log unless separate debug logs are specified with `DEBUGLOG` in each vendor daemon's options file. Having one common debug log makes it harder to debug a single vendor daemon's problem.
- Maximizes licensing load to one system and one license server manager.

Starting the License Server

In this configuration, you start one license server on a single machine. The license server uses multiple license files (and hence possibly multiple vendor daemons). Use `lmadmin` or `lmgrd` as the license server manager.

Using lmadmin

When using `lmadmin`, you can start the license server using the `lmadmin` user interface or a command line.

Starting the License Server Using the User Interface



Task *To use the `lmadmin` user interface to start the license server:*

1. At a command prompt from the `lmadmin` installation directory on the machine, enter **lmadmin**. No special command-line options are required.
2. Open the `lmadmin` user interface. For instructions, see [Accessing the License Server Management Interface in Chapter 9, "License Server Manager "lmadmin".](#)
3. From the `lmadmin` user interface's main window, click **Administration** to open the Administration page, and sign in with your administrator credentials.
4. Go to the Vendor Daemon Configuration tab.
5. Click **Import License File**.
6. Select and import the license file.



Note • A status message displayed on the `lmadmin` user interface lists any follow-up steps you need to perform after the import. If the message requests that you start (or restart) the vendor daemon, click **Administer** for the specific vendor daemon on the Vendor Daemon Configuration tab; and then click **Stop** or **Start**.

7. Repeat the import process for each license file you want to import.
8. Close down the `lmadmin` user interface.

Starting the License Server Using the Command Line



Task *To use the command line to start the license server:*

1. Open a command window on the machine.
2. At a command prompt from the `lmadmin` installation directory, enter the following to import the license files:

```
lmadmin -import <license_file_list>
```

where `<license_file_list>` is the list of license files to import, as described in [Managing Multiple License Files](#).



Note • Use the `-force` option with `-import` only if you want to overwrite `server.xml` settings previously defined for the vendor daemons specified in the license files.

3. Enter **lmadmin** (and any `lmadmin` options you might need) to start the license server. For a description of options, see [lmadmin Command-line Arguments](#) in Chapter 9, “License Server Manager “lmadmin”.”

Using lmgrd



Task

To start the license server:

Enter the following command:

```
lmgrd -c <common_license_directory>
```

where `<common_license_directory>` is the directory containing the license files, as described in [Managing Multiple License Files](#). (By specifying the directory, you do not need to enumerate each license file name on the `lmgrd` command line.)

`lmgrd` processes all files with the `.lic` extension in the directory and then starts all vendor daemons to which the files refer.

See Also

[Managing Multiple License Files](#)

[Capturing Debug Log Output for a Particular Vendor Daemon](#)

Managing Multiple License Files

As described in the previous sections, both `lmadmin` and `lmgrd` handle multiple license files. This section briefly describes how the license server managers handle multiple files and how you set up a multiple-license-file list.

Managing Multiple File in lmadmin

When using **lmadmin** as your license server manager, you can use the `lmadmin` user interface to import the license files one at a time or use the command-line `-import` option (and the `license_file_list`) to specify the files. See the previous sections for details.

Managing Multiple Files in lmgrd

When using `lmgrd` as the license server manager, you can manage multiple license files that are on the same system via a license search path. A license search path is specified two ways:

- By using the `-c` option to `lmgrd`:

```
lmgrd -c license_file_list [other lmgrd options]
```

- By defining the `LM_LICENSE_FILE` environment variable within the scope of the `lmgrd` process’s environment.

lmgrd builds up an internal license search path when it starts up by parsing each entry in the order listed.

Defining the License File List

Install the license files in convenient locations on the system, and then define the `license_file_list`.

Wherever `license_file_list` is specified, it consists of a list of one or more of the following components. (Use a colon (:) to separate the license file names on UNIX; on Windows, use a semicolon (;).)

- The full path to the license file
- A directory containing one or more license files with a **.lic** extension
- The license server port. Use one of the following:
 - A `port@host` setting, where `port` and `host` are the TCP/IP port number and host name from the SERVER line in the license file.
 - The shortcut specification, `@host`, if the license file SERVER line uses a default TCP/IP port or specifies a port in the default port range (27000–27009).
 - A comma separated list of three `port@host` specifiers denoting a license servers configured for three-server redundancy (for example, `port1@host1,port2@host2,port3@host3`).

Some scenarios where a license search path is used include those described in [Multiple Systems, One System with Multiple License Server Instances](#), or [One System with One License Server and Multiple License Files](#).

See Also

[Setting the License Search Path Using an Environment Variable](#)

[Ensuring License Availability](#)

[Environment Variables](#)

Additional Considerations

Combining License Files


If you have two or more products whose licenses are intended for the same system, as specified by their SERVER lines, you may be able to combine the license files into a single license file. This has advantages if you are using `lmgrd` as your license server manager.



Note • `lmadmin` supports the use of a combined license file. However, use of such a file is redundant when you can simply use the `lmadmin` user interface to add (import) any number of license files. Once a license file is imported, `lmadmin` manages it.

The license files for the models described in [One System with Multiple License Server Instances](#) and [One System with One License Server and Multiple License Files](#) could be combined if they met certain criteria. See [Criteria for Combining License Files](#). Figure 18-4 shows one possible scenario using a combined license file.

Figure 18-4: One Imgrd, One License File



Advantages

- A single license file to administer.
- Once the files are combined, there is low administrative overhead.

Disadvantage

- Careful planning must be given in combining license lines from multiple software publishers into one file, initially and over time.

Starting the License Server



Task **To start the license server:**

Invoke the license server manager once on the system.

```
Imgrd -c combined_license_file
```

Criteria for Combining License Files

Your product's license files define the license server systems by host name and hostid in the SERVER lines in the license file. License files are candidates for combining under the following conditions:

- The number of SERVER lines in each file is the same.

- The hostid field of each SERVER line in one file *exactly* matches the hostid field of each SERVER line in the other file.

Some possible reasons license files may not be compatible are:


- License files are set up to run on different server systems, so hostids are different.
- One file is set up for a single license server (has only one SERVER line), the other is set up for a three-server redundancy (has three SERVER lines).
- Hostids for the same system use different hostid types. For example, the SERVER line in one license file uses INTERNET= for its hostid type and the other file uses the ethernet MAC address for its hostid type.

If your license files are compatible as described above, then you have the option of combining license files as summarized in [Figure 18-4](#) and below in [How to Combine License Files](#). Note that you are not required to combine compatible license files. There is no performance or system-load penalty for not combining the files.

How to Combine License Files

If your license files are compatible, use any text editor to combine them. To combine license files, read all of the compatible license files into one file, then edit out the extra SERVER lines so that only one set of SERVER lines remains. Save the resulting data, and you have your combined license file. [Figure 18-5](#) shows an example of combining license files.

Figure 18-5: Combining License Files



Version Component Compatibility

When one license server manager manages multiple vendor daemons, it may be the case that those vendor daemons do not use the same version of FlexNet Publisher. By observing the FlexNet Publisher version compatibility rules described in [Version Compatibility Between Components](#) you are assured that all of your FlexNet Publisher components are compatible.

You can maintain multiple versions of FlexEnabled applications in the enterprise. The vendor daemon for an application must be at least the same version as the FlexNet Publisher version used in the FlexEnabled application.

19

Troubleshooting

This section documents areas of the license server that have given customers difficulty in the past.

General Troubleshooting Hints

This list provides some general debugging information:

- When you start the license server be sure that you direct the output into a local log file where you can examine it. The log file often contains useful information. Examine it when you have a problem, and be prepared to answer questions about it when you talk to a support person.
- If the license server appears to have started correctly (which you can determine from the log file), try running `lmstat -a` and `lmdiag` to see if that program has the same problem as your application.
- If your application is version 4.1 or later (version 5 or later on Windows), you can use the `FLEXLM_DIAGNOSTICS` environment variable. Set `FLEXLM_DIAGNOSTICS` to 1, 2, or 3. A setting of 3 gives more information than 2, 2 gives more information than 1 (in particular, the feature name that was denied). See [FLEXLM_DIAGNOSTICS](#) for more information.
- When you talk to a support person, be prepared with answers to the following questions:

- What kind of system is your license server running on?
- What version of the operating system?
- What system and operating system is the application running on?
- What version of FlexNet Publisher does the FlexEnabled application use?

Use the `lmver` script, or, on UNIX, execute the following command on your license server manager, vendor daemon, and application:

```
strings binary_name | grep Copy
```

Alternatives are: for `lmadmin`, use the command `lmadmin -version`; for `lmgrd` and the vendor daemon use the `-v` argument, for example `lmgrd -v`.

- What error or warning messages appear in the log file?

- Did the server start correctly? Look for a message such as:
server xyz started for: feature1 feature2.
- What is the output from running `lmstat -a`?
- Are you running other FlexEnabled products?
- Are you using a combined license file or separate license files?
- Are you using three-server redundancy (i.e. there are multiple SERVER lines in your license file)?

FLEXLM_DIAGNOSTICS



Note • The ability for FlexNet Publisher to produce diagnostic output is controlled by your software publisher.

FLEXLM_DIAGNOSTICS is an environment variable that causes the application to produce diagnostic information when a checkout is denied. The format of the diagnostic information may change over time.

On UNIX, the diagnostic output goes to `stderr`.

On Windows, the output is a file called **flexpid.log** (where `pid` is the application's process ID).

Level 1 Content

If FLEXLM_DIAGNOSTICS is set to 1, then the standard FlexNet Publisher error message is be presented, plus a complete list of license files that the application tried to use. For example:

```
setenv FLEXLM_DIAGNOSTICS 1
FlexNet checkout error: Cannot find license file (-1,73:2) No such file or directory
license file(s): /usr/myproduct/licenses/testing.lic license.lic
```

Level 2 Content

If FLEXLM_DIAGNOSTICS is set to 2, then, in addition to level 1 output, the checkout arguments are presented. For example:

```
setenv FLEXLM_DIAGNOSTICS 2
FlexNet checkout error: No such feature exists (-5,116:2) No such file or directory
license file(s): /usr/myproduct/licenses/testing.lic license.lic
lm_checkout("f1", 1.0, 1, 0x0, ..., 0x4000)
```

Note that the error message actually contains two separate problems, which both occurred during the checkout:

- There is no such feature in the license it did find.
- It was unable to find the other license file, which is what produces the message `No such file or directory`.

This is a description of the arguments to **lm_checkout**:

`lm_checkout(feature, version, num_lic, queue_flag, ..., dupgroup_mask)`

where:

Table 19-1 • lm_checkout Arguments

Argument	Description
feature	The requested feature.
version	The requested version. The license file must contain a version \geq the requested version.
num_lic	Number of licenses requested. Usually 1.
queue_flag	If 0, no queueing If 1, queue for license ("blocking" queue) If 2, queue for licenses, but return to application ("non-blocking" queue)
dupgroup_mask	Indicates duplicate grouping, also called license sharing. User, host, and display are as shown by <code>lmstat -a</code> .

Level 3 Content (Version 6.0 or Later Only)

If `FLEXLM_DIAGNOSTICS` is set to 3, then, in addition to level 1 and 2 output, if a checkout is successful, information is printed explaining how the license was granted:

```
setenv FLEXLM_DIAGNOSTICS 3
app
Checkout succeeded: f0/14263EAEA8E0
License file: ./servtest.lic
No server used
app2
Checkout succeeded: f1/BC64A7B120AE
License file: @localhost
License Server Machine: @localhost
app3
Checkout succeeded: f1/BC64A7B120AE
License file: servtest.lic
License Server Machine: @speedy
```

Note that the feature name and license key are printed, along with the license file location (or host name if `@host` were used) and host name of the server, where applicable.

20

Error Codes

This section documents FlexNet Publisher error messages, including general format and error message descriptions.

Error Message Format

FlexNet Publisher error messages presented by applications have the multiple components, which are described in the following table. An error message may also contain other optional supporting information.

Table 20-1 • FlexNet Publisher Error Message Components

Component	Description	Required
Error Number	A positive or negative integer that identifies the error.	
Error Text	Sentence that summarizes the issue.	
Error Explanation	Paragraph that explains the problem and provides possible solutions or workarounds.	
Minor Error Number	A positive integer. These numbers are unique error identifiers and are used by software publishers for more advanced support assistance. Their meaning is not documented.	
System Error Number	Error code last set by the operating system.	
System Error Explanation	Sentence that explains the system error.	

These error messages may occur in two formats available with FlexNet Publisher, or they may appear in a format customized by the application.

Format 1 (short)

FlexNet error text (*Lm_errno*, *minor_num*[:*sys_errno*]) [*sys_error_text*]

The error information may be missing.

Example

Can't connect to license server machine (-15,12:61) Connection refused

Format 2 (long)

FlexNet error text
FlexNet error explanation
[Optional Supporting information]
FlexNet error: *Lm_errno*, *minor_num*. [System Error: *sys_errno*] ["*system_error_text*"]

Example

Cannot connect to license server system
The server (lmgrd) has not been started yet, or
the wrong port@host or license file is being used, or the
port or hostname in the license file has been changed.
Feature: f1
Server name: localhost
License path: @localhost:license.dat:./*.lic
FlexNet error: -15,12. System Error: 61 "Connection refused"

Error Code Descriptions

The following table lists the most common errors produced by FlexEnabled applications.

Table 20-2 • Error Codes

Error Code	Description
24	Insufficient privilege to complete initialization.
23	Attempt to access server trusted storage from client app, or vice-versa.
22	Service configuration or dependency issue. See event log for Windows error code.
21	lc_flexinit failed because there were insufficient rights to start the FlexNet Licensing Service. Resolve this by setting the service to start automatically.
20	FlexNet Licensing Service is not installed.
13	Computed path to required file is too long for OS X operating system.
12	Invalid bundle ID on OS X operating system.
11	Framework specified by bundle ID was not loaded.

Table 20-2 • Error Codes

Error Code	Description
10	Error creating path from URL.
9	Error creating URL.
8	Path string not specified in UTF-8 format.
7	A call to <code>lc_flexinit</code> is not allowed after a call to <code>lc_flexinit_cleanup</code> .
6	Activation utility has not been processed using the <code>preptool</code> , or the activation library for the activation utility cannot be found.
5	Unable to allocate resources.
4	Initialization failed.
3	Unsupported version of the operating system.
2	Unable to load activation library.
1	Unable to find activation library.
-1	Cannot find license file.
-2	Invalid license file syntax.
-3	No license server system for this feature.
-4	Licensed number of users already reached.
-5	No such feature exists.
-6	No TCP/IP port number in license file, and FlexNet Licensing Service does not exist. (pre-v6 only)
-7	No socket connection to license server manager service.
-8	Invalid (inconsistent) license key or signature. The license key/signature and data for the feature do not match. This usually happens when a license file has been altered.
-9	Invalid host. The <code>hostid</code> of this system does not match the <code>hostid</code> specified in the license file.
-10	Feature has expired.
-11	Invalid date format in license file.

Table 20-2 • Error Codes

Error Code	Description
-12	Invalid returned data from license server system.
-13	No SERVER lines in license file.
-14	Cannot find SERVER host name in network database. The lookup for the host name on the SERVER line in the license file failed. This often happens when NIS or DNS or the hosts file is incorrect. Work around: Use IP address (for example, 123.456.789.123) instead of host name.
-15	Cannot connect to license server system. The server (lmadmin or lmgrd) has not been started yet, or the wrong <i>port@host</i> or license file is being used, or the TCP/IP port or host name in the license file has been changed. Windows XP SP2 platforms have a limit on the number of TCP/IP connection attempts per second that can be made, which your application may have exceeded. Refer to the manufacturer's documentation on how to change this limit.
-16	Cannot read data from license server system.
-17	Cannot write data to license server system.
-18	License server system does not support this feature.
-19	Error in select system call.
-20	License server system busy (no majority).
-21	License file does not support this version.
-22	Feature checkin failure detected at license server system.
-23	License server system temporarily busy (new server connecting).
-24	Users are queued for this feature.
-25	License server system does not support this version of this feature.
-26	Request for more licenses than this feature supports.
-29	Cannot find ethernet device.
-30	Cannot read license file.
-31	Feature start date is in the future.
-32	No such attribute.

Table 20-2 • Error Codes

Error Code	Description
-33	Bad encryption handshake with vendor daemon.
-34	Clock difference too large between client and license server system.
-35	In the queue for this feature.
-36	Feature database corrupted in vendor daemon.
-37	Duplicate selection mismatch for this feature. Obsolete with version 8.0 or later vendor daemon.
-38	User/host on EXCLUDE list for feature.
-39	User/host not on INCLUDE list for feature.
-40	Cannot allocate dynamic memory.
-41	Feature was never checked out.
-42	Invalid parameter.
-47	Clock setting check not available in vendor daemon.
-52	Vendor daemon did not respond within timeout interval.
-53	Checkout request rejected by vendor-defined checkout filter.
-54	No FEATURESET line in license file.
-55	Incorrect FEATURESET line in license file.
-56	Cannot compute FEATURESET data from license file.
-57	socket call failed.
-59	Message checksum failure.
-60	License server system message checksum failure.
-61	Cannot read license file data from license server system.
-62	Network software (TCP/IP) not available.
-63	You are not a license administrator.
-64	Imremove request before the minimum Imremove interval.
-67	No licenses available to borrow.

Table 20-2 • Error Codes

Error Code	Description
-68	License BORROW support not enabled.
-69	FLOAT_OK can't run standalone on license server system.
-71	Invalid TZ environment variable.
-73	Local checkout filter rejected request.
-74	Attempt to read beyond end of license file path.
-75	SYS\$SETIMR call failed (VMS). Indicates an error due to an operating system failure.
-76	Internal <i>FlexNet Licensing</i> error. Please report error to Flexera Software.
-77	Bad version number must be floating-point number with no letters.
-82	Invalid PACKAGE line in license file.
-83	<i>FlexNet Licensing</i> version of client newer than server.
-84	USER_BASED license has no specified users; see license server system log.
-85	License server system doesn't support this request.
-87	Checkout exceeds MAX specified in options file.
-88	System clock has been set back.
-89	This platform not authorized by license.
-90	Future license file format or misspelling in license file. The file was issued for a later version of FlexNet Licensing than this program understands.
-91	Encryption seeds are non-unique.
-92	Feature removed during <code>lmrread</code> , or wrong SERVER line hostid.
-93	This feature is available in a different license pool. This is a warning condition. The server has pooled one or more INCREMENT lines into a single pool, and the request was made on an INCREMENT line that has been pooled.
-94	Attempt to generate license with incompatible attributes.
-95	Network connect to THIS_HOST failed. Change this_host on the SERVER line in the license file to the actual host name.

Table 20-2 • Error Codes

Error Code	Description
-96	License server machine is down or not responding. See the system administrator about starting the server, or make sure that you're referring to the right host (see LM_LICENSE_FILE environment variable).
-97	The desired vendor daemon is down. 1) Check the ladmin or lmgrd log file, or 2) Try lmreread.
-98	This FEATURE line can't be converted to decimal format.
-99	The decimal format license is typed incorrectly.
-100	Cannot remove a linger license.
-101	All licenses are reserved for others. The system administrator has reserved all the licenses for others. Reservations are made in the options file. The server must be restarted for options file changes to take effect.
-102	A FLEXid borrow error occurred.
-103	Terminal Server remote client not allowed.
-104	Cannot borrow that long.
-105	Feature already returned to license server.
-106	License server system out of network connections. The vendor daemon can't handle any more users. See the debug log for further information.
-110	Cannot read dongle: check dongle or driver. Either the dongle is unattached, or the necessary software driver for this dongle type is not installed.
-112	Missing dongle driver. In order to read the FLEXID hostid, the correct driver must be installed. These drivers are available from your software publisher.
-114	SIGN= keyword required, but missing from license certificate. You need to obtain a SIGN= version of this license from your publisher.
-115	Error in Public Key package.
-116	TRL not supported for this platform.
-117	BORROW failed.

Table 20-2 • Error Codes

Error Code	Description
-118	BORROW period expired.
-119	1mdown and 1mreread must be run on license server.
-120	Cannot 1mdown the server when licenses are borrowed.
-121	FLOAT_OK requires exactly one FLEXid hostid.
-122	Unable to delete local borrow info.
-123	Returning a borrowed license early is not supported. Contact the publisher for further details.
-124	Error returning borrowed license.
-125	A PACKAGE component must be specified.
-126	Composite hostid not initialized.
-127	A item needed for the composite hostid is missing or invalid.
-128	Error, borrowed license doesn't match any known server license.
-135	Error enabling the event log.
-136	Event logging is disabled.
-137	Error writing to the event log.
-139	Communications timeout.
-140	Bad message command.
-141	Error writing to socket. Peer has closed socket.
-142	Error, cannot generate version specific license tied to a single hostid, which is composite.
-143	Version-specific signatures are not supported for uncounted licenses.
-144	License template contains redundant signature specifiers.
-145	Bad V71_LK signature.
-146	Bad V71_SIGN signature.
-147	Bad V80_LK signature.

Table 20-2 • Error Codes

Error Code	Description
-148	Bad V80_SIGN signature.
-149	Bad V81_LK signature.
-150	Bad V81_SIGN signature.
-151	Bad V81_SIGN2 signature.
-152	Bad V84_LK signature.
-153	Bad V84_SIGN signature.
-154	Bad V84_SIGN2 signature.
-155	License key required but missing from the license certificate. The application requires a license key in the license certificate. You need to obtain a license key version of this certificate from your publisher.
-156	Invalid signature specified with the AUTH= keyword.
-157	Trusted storage has been compromised; repair needed. Contact your publisher for repair instructions.
-158	Trusted storage open failure. Contact your publisher for further information.
-159	Invalid fulfillment record. Contact your publisher for further information.
-160	Invalid activation request received. Contact your publisher for further information.
-161	No fulfillment exists in trusted storage which matches the request. Contact your publisher for further information.
-162	Invalid activation response received. Contact your publisher for further information.
-163	Cannot return the specified activation. Contact your publisher for further information.
-164	Return count(s) would exceed the maximum for the fulfillment. Contact your publisher for further information.
-165	No repair count left. Contact your publisher for further repair authorization.
-166	Specified operation not allowed. Contact your publisher for further information.
-167	The requested activation has been denied because the user or host is excluded from activating this entitlement by a specification in the options file.

Table 20-2 • Error Codes

Error Code	Description
-168	The options file contains include specifications for the entitlement, and this user or host is not included in these specifications.
-169	Activation error. Contact your publisher for further information.
-170	Invalid date format in trusted storage. Can be caused by setting your system clock to an earlier date. Check that your system clock is set to the current date and time.
-171	Message encryption failed. Internal error. Report issue to Flexera Software.
-172	Message decryption failed. Internal error. Report issue to Flexera Software.
-173	Bad filter context. Internal error. Report issue to Flexera Software.
-174	SUPERSEDE feature conflict. Contact your publisher for further information.
-175	Invalid SUPERSEDE_SIGN syntax. Contact your publisher for further information.
-176	SUPERSEDE_SIGN does not contain a feature name and license signature. Contact your publisher for further information.
-177	ONE_TS_OK is not supported in this Windows Platform.
-178	Internal error. Report issue to Flexera Software. When more than one remote desktop checkout is performed expect -178: Internal error if more than one terminal server remote client checkout occurred. If it is not more than one remote desktop checkout, then report the issue to Flexera Software.
-179	Only one terminal server remote client checkout is allowed for this feature.
-180	Internal error. Report issue to Flexera Software.
-181	Internal error. Report issue to Flexera Software.
-182	Internal error. Report issue to Flexera Software.
-183	More than one ethernet hostid not supported in composite hostid definition. Contact your publisher for further information.
-184	The number of characters in the license file paths exceeds the permissible limit. There is a limit on the number of license files that can be used by a license server manager. This limit is on the number of characters in the combined license file paths to the license files: <ul style="list-style-type: none"> ● UNIX—40,960 characters ● Windows—20,400 characters Reduce the number of license files, or relocate them so that the paths are shorter.

Table 20-2 • Error Codes

Error Code	Description
-187	The time zone information could not be obtained. A license that is time zone limited could not be checked out because time zone information could not be obtained for the machine on which the license is required. Contact your publisher for further information.
-188	License client time zone not authorized for license rights. A license that is time zone limited could not be checked out because the time zone of the machine on which the license is required does not match the time zone specified in the license.
-190	Feature can be checked out from Physical machine only. The license specifies that it cannot be used on a virtual machine: The FlexEnabled application is installed on a virtual machine so checkout has been denied. Install the FlexEnabled application on a physical machine.
-191	FEATURE can be checked out from Virtual machine only. The license specifies that it cannot be used on a physical machine. The FlexEnabled application is installed on a physical machine so checkout has been denied. Install the FlexEnabled application on a virtual machine.
-192	VM platform not authorized by license.
-193	FNP vendor keys do not support Virtualization feature.
-194	Checkout request denied as it exceeds the MAX limit specified in the options file.
-195	Binding agent API - Internal error.
-196	Binding agent communication error
-197	Invalid Binding agent version.
-201	Invalid IP address used while overriding. The IP address specified for the LM_A_INTERNET_OVERRIDE attribute, used to override the existing IP address, is invalid.
-220	Failed to get licenses from trusted storage.

21

Report Log File

The license server produces both report log files and debug log files. The focus of this section is report log files. For information on debug log files see [Debug Log File](#).

The report log file contains feature usage information and is generated by the vendor daemon. However, a vendor daemon does not write report logs by default; this action must be enabled. The data in report logs is compressed, authenticated, and organized into a repository.

Use Flexera Software's software license administration solution, FlexNet Manager, to gain exceptional visibility into license usage data and to create insightful reports on critical information like license availability and usage. FlexNet Manager can be fully automated to run these reports on schedule and can be used to track license servers and usage across a heterogeneous network of server including Windows NT, Linux and UNIX. Contact Flexera Software at www.flexerasoftware.com for more details on how to obtain an evaluation copy of FlexNet Manager for your enterprise.

Managing Report Log Output

As a vendor daemon runs for a period of time, the volume of report log output increases. If you have a lot of license activity, these log files grow very large. You need to consider where to put these files and how often to rotate and archive them. Therefore, it may be necessary to rotate or switch report log output into different files over time, each file containing license activity over a particular period of time.

Report log data is collected by the vendor daemon into an internal data buffer area before being flushed to the output file. The daemon's internal buffer is flushed once a minute or whenever it gets full, whichever occurs first. To ensure the freshest data possible in the report log file, flush the buffer on demand with the `lrmreread` command. Use standard file compression tools to reduce the size of a report log file when it is no longer being written.

To avoid corruption and for performance, it is suggested that the vendor daemon write its report log to a file on a disk local to the system running the vendor daemon. Each vendor daemon must write to its own report log file.

Enabling Report Log Output for a Vendor Daemon

There are two ways to enable report logging for a particular vendor daemon either before or after starting the license server.

- Add the REPORTLOG line to the options file for that vendor daemon. See [REPORTLOG](#) for more details.
- Invoke `lmswitchr` on the vendor daemon. See [lmswitchr](#) for more details.

Redirecting Report Log Output for a Vendor Daemon

The report log output for a particular vendor daemon can be moved into separate files, each file representing activity over a different period of time. There are three ways in which to do this whether the vendor daemon is running or not:

- Change the REPORTLOG line in the vendor daemon's options file and reread its options file by invoking `lmreread` (version 8.0 or later vendor daemon) or restart.
- Invoke `lmswitchr` on the vendor daemon. See [lmswitchr](#) for more details.
- Invoke `lmnewlog` on the vendor daemon. Requires a version 7.1 or later vendor daemon. See [lmnewlog](#) for more details.

22

Debug Log File

The license server produces both debug log files and report log files. For information on report log files, see [Report Log File](#).

A debug log file contains status and error messages useful for debugging the license server. The `lmgrd` debug log displays the server's system date, time, and time zone at the beginning of a log. A license server always generates debug log output. Some of the debug log output describes events specific to `lmadmin` or `lmgrd` and some of the debug log output describes events specific to each vendor daemon.

Managing Debug Log Output

As the license server manager and its vendor daemons run for a period of time, the volume of this output increases. As it gets older, the value of the debug log output decreases; therefore, it may be necessary for you to separate old debug log output from current output; either archive or delete the old output.

For performance, it is suggested that each debug log file be on a disk that is local to the system that is running the license server manager and its vendor daemons. However, if the debug log file must be on a remotely-mounted disk and you find that the license server is too slow, start `lmgrd` with the `-nfs_log` option to improve performance.

See [Debug Log Messages](#) for a description of the debug log output format.

Capturing Debug Log Output for a License Server

If you are using `lmadmin` as your license server manager, separate log files are created for `lmadmin` and each vendor daemon that it manages. The log files are written to the **logs** directory within the **lmadmin** install directory (default on non-Windows platforms) or the `<lmadmin_runtimedata_dir>\logs` folder (default on Windows platforms). However, you can use the `-logDir` option on the command line to change the location to which `lmadmin` writes **lmadmin.log**. See [lmadmin Command-line Arguments](#) for details.

By default, `lmgrd` and the vendor daemons it manages write debug log output to standard out. To put this debug log output in a file, either redirect the output of the license server to a file or start `lmgrd` with the `-l debug_log_path` option. See [lmgrd Command-Line Syntax](#) for more information.

Capturing Debug Log Output for a Particular Vendor Daemon

The debug log output from different vendor daemons controlled by the same license server can be written to their own files (version 8.0 and later vendor daemon). There are three ways to do this:

- If you are using `lmadmin` as your license server manager, you configure the location and file name from the Vendor Daemon Configuration screen. See on-line help for information on Vendor Daemon Log.
- Add the `DEBUGLOG` line to the options file for each vendor daemon. See [DEBUGLOG](#) for more details.
- Invoke `lmswitch` on the vendor daemon. See [lmswitch](#) for more details.

Note that `lmgrd` writes its own debug log output to standard out.

Redirecting Debug Log Output for a Running Vendor Daemon

It is possible to redirect the debug log output for a particular vendor daemon to a different file. There are two ways to do this:

- Change the `DEBUGLOG` line to the options file for the vendor daemon and reread its options file by invoking `lmreread`. See [DEBUGLOG](#) for more details.
- Invoke `lmswitch` on the vendor daemon. See [lmswitch](#) for more details.

Limiting Debug Log Output for a Vendor Daemon

By default, debug log output contains all events. To limit the events that are logged for a particular vendor daemon, add a `NOLOG` line to the options file of that vendor daemon. One of the reasons you may want to limit the events that are logged is to reduce the size of the debug log output.

See Also
[NOLOG](#)

License Server Diagnostics in the Debug Log

Enhanced license server diagnostics will now be emitted in the license server debug log. Additional diagnostics are prefixed by "`(@lmgrd-SLOG@)`" for the `lmgrd` and "`(@<vendor>-SLOG@)`" for the Vendor Daemon, facilitating easy grep-like extraction from the debug-log. The Vendor Daemon would emit the additional diagnostics when run with `lmgrd` or `lmadmin`. These diagnostics are intended to assist publishers and Flexera Software diagnose license server issues. These diagnostics include:

- For `lmgrd`:
Start timestamp, Version, ProcessID, Network Info (IPv4/IPv6 interface, listening port), command-line options, list of license files, whether the license server is running as a Windows service.
- For Vendor Daemon:

Start timestamp, Version, ProcessID, Network infor(Ipv4/Ipv6 interface, listening port, select timeout of vendor daemon), Vendor daemon name, options fileused, Trusted Storage accessed (yes/no). Host name, Virtual/physical environment, (limited) hypervisor info if virtual, #Restarts of vendor daemon since lmgrd startup, #Rereads since vendor daemon (re0 start, Last reread time, Reread initiation type (automatic versus 1mreread)

Every 4 hours (and at vendor daemon shutdown) the following performance data are logged:

Details of the 10 peak client transactions (including client hostname, user, transaction time, concurrent clients at time of transaction, memory usage (Windows only)), **Peak concurrent clients served**, **High watermark memory usage (Windows only)**, **Transaction time for last 10 transactions**.

Debug Log Messages

FlexNet Publisher processes generate debug log files in the following format:

hh:mm:ss (daemon) message

where:

Table 22-1 • Debug Log Messages

Message	Description
<i>hh:mm:ss</i>	Time that the message was logged.
daemon	Either 1madmin, 1mgrd or the vendor daemon name. In the case where a single copy of the daemon cannot handle all of the requested licenses, an optional "_" followed by a number indicates that this message comes from a forked daemon.
message	The text of the message.

The debug log files can be used to diagnose configuration problems and vendor-daemon software errors.



Note • A debug log file cannot be used for usage reporting with FlexNet Manager.

Informational Messages

Table 22-2 lists the various informational messages used within FlexNet Publisher.

Table 22-2 • Information Messages

Message	Description
Connected to host	This daemon is connected to its peer on host.
CONNECTED, master is host	The license daemons log this message when a quorum is up and everyone has selected a master.
DENIED: num_lic feature to user	user was denied access to num_lic licenses of feature.

Table 22-2 • Information Messages

Message	Description
EXITING DUE TO SIGNAL nnn EXITING with code nnn	All daemons list the reason that the daemon has exited.
EXPIRED: feature	feature has passed its expiration date.
IN: "feature" user (num_lic licenses)	user has checked in num_lic licenses of feature.
Lost connection to host	A daemon can no longer communicate with its peer on node host, which can cause the clients to have to reconnect, or cause the number of daemons to go below the minimum number, in which case clients may start exiting. If the license daemons lose the connection to the master, they kill all the vendor daemons; vendor daemons shut themselves down.
Lost quorum	The daemon lost quorum, so it processes only connection requests from other daemons.
MULTIPLE vendor servers running. Kill and restart license daemon.	The license server manager has detected that multiple vendor daemons with the same vendor name are running. Shutdown lmadmin or lmgrd and all vendor daemons and then restart lmadmin or lmgrd.
OUT: feature user (num_lic licenses)	user has checked out num_lic licenses of feature.
RESERVE feature for USER user RESERVE feature for HOST host	A license of feature is reserved for either user or host.
REStarted vendor (internet port nnn)	Vendor daemon vendor was restarted at TCP/IP port nnn.
Retrying socket bind (address in use)	The license servers try to bind their sockets for approximately six minutes if they detect "address in use" errors.
Selected (EXISTING) master host.	This license daemon has selected an existing master <i>host</i> as the master.
SERVER shutdown requested.	A daemon was requested to shut down via a user-generated kill command.
Server started on host for: feature_list	A (possibly new) server was started for the features listed.
Shutting down vendor	The license server manager is shutting down the vendor daemon vendor.
SIGCHLD received. Killing child servers.	A vendor daemon logs this message when a shutdown was requested by the license daemon.
Started vendor	The license server manager logs this message whenever it starts a new vendor daemon.

Table 22-2 • Information Messages

Message	Description
TIMESTAMP	A vendor daemon logs this message at regular intervals. The default interval between vendor daemon timestamps is 6 hours 5 minutes. A license server manager (lmadmin or lmgrd) logs this message at regular intervals. The default interval between license server manager timestamps is 6 hours.
Trying to connect to host	The daemon is attempting a connection to host.
UPGRADE: "<feature>"(x->y licenses)	Identical checkout requests (using the LM_A_CHECKOUT_DATA attribute) has incremented the number of licenses checked out for a given feature within the same license job. The previous request checked out x licenses, while latest request has checked out y licenses, for a total of x +y licenses checked out for the feature.

Configuration Problem Messages

Table 22-3 lists configuration problem messages found in FlexNet Publisher.

Table 22-3 • Configuration Problem Messages

Message	Description
host: Not a valid server host, exiting	This daemon was run on an invalid host name.
host: Wrong hostid, exiting	The hostid is wrong for host.
BAD CODE for feature	The specified feature name has a bad license key or signature. It was probably typed in wrong, or modified by the end user.
CANNOT OPEN options file	The options file specified in the license file could not be opened.
Couldn't find a master	The daemons could not agree on a master.
License daemon: lost all connections	This message is logged when all the connections to a server are lost, which often indicates a network problem.
Lost lock, exiting Error closing lock file Unable to re-open lock file	The vendor daemon has a problem with its lock file, usually because of an attempt to run more than one copy of the daemon on a single node. Locate the other daemon that is running via a <code>ps</code> command, and kill it with <code>kill -9</code> .
No DAEMON line for vendor	The license file does not contain a DAEMON or VENDOR line for vendor.

Table 22-3 • Configuration Problem Messages

Message	Description
No DAEMON lines, exiting	The license daemon logs this message if there are no DAEMON or VENDOR lines in the license file. Because there are no vendor daemons to start, there is nothing for the license daemon to do.
No features to serve!	A vendor daemon found no features to serve. This could be caused by a corrupted or incorrectly entered license file.
UNSUPPORTED FEATURE request: feature by user	The user has requested a feature that this vendor daemon does not support. This can happen for a number of reasons: the license file is bad, the feature has expired, or the daemon is accessing the wrong license file.
Unknown host: host	The host name specified on a SERVER line in the license file does not exist in the network database (probably /etc/hosts).

Daemon Software Error Messages

Table 22-4 lists various daemon software error messages:

Table 22-4 • Daemon Software Error Messages

Message	Description
accept: message	An error was detected in the accept system call.
Can't allocate server table space	A malloc error. Check swap space.
Connection to <i>host</i> TIMED OUT	The daemon could not connect to host.
Illegal connection request to <i>vendor</i>	A connection request was made to vendor, but this vendor daemon is not vendor.
read: error message	An error in a "read" system call was detected.
select: message	An error in a "select" system call was detected. This is usually a sign of a system networking failure.
Server exiting	The server is exiting. This is normally due to an error.

Identifying FlexNet Publisher Versions

Version Compatibility Between Components

In general, always use the latest version of `lmadmin`, `lmgrd`, `lmutil`, and `lmtools`, all of which are available from www.flexerasoftware.com, to exploit the enhancements available in the most recent versions of FlexNet Licensing. However, some enhancements require a vendor daemon built with a newer version of FlexNet Publisher, and yet others require a FlexEnabled application built with a newer version of FlexNet Publisher. Contact your software publisher for the latest version of their vendor daemon.

The rules about FlexNet Licensing component version compatibility are summarized as:

- Version of `lmutil/lmtools` must be \geq
- Version of `lmadmin` (or `lmgrd`), which must be \geq



Note • `lmadmin` can only be used with components with a version of 9.2 or later.

- Version of vendor daemon, which must be \geq
- Version of the client library linked to the FlexEnabled application, which must be \geq
- Activation utility, which must be \geq
- Version of license file format

Except for the license file, use `lmver` to discover the version of all these components. For the vendor daemon, `lmgrd`, and `lmutil`, you can also use the `-v` argument to print the version.

Determining the License File Version

The following rules apply to individual FEATURE, INCREMENT or UPGRADE lines. It is possible to have a mix of versions in a single file. Only the features that a particular application checks out determine the version of the license for that feature.

Table 23-1 • Determining the License File Version

Version	Description
Version 2	Blank quotes or a quoted string at the end of the FEATURE line.
>= Version 3	INCREMENT or UPGRADE line.
>= Version 4	OVERDRAFT, DUP_GROUP, INTERNET, or PACKAGE appear.
>= Version 5	SUPERSEDE, ISSUED, USER_BASED, HOST_BASED, or SN appear.
>= Version 6	START appears.
>= Version 7.1	SIGN= keyword appears.
>= Version 8.0	BORROW, FLOAT_OK, and TS_OK appear.
>= Version 8.1	SUITE_RESERVED appears.
>= Version 8.4	COMPOSITE appears.
>= Version 11.5	ONE_TS_OK and SUPERSEDE_SIGN appear.
>=Version 11.7	VM_PLATFORMS and TZ appear.

Environment Variables

Environment variables are not required in order to use FlexEnabled applications. Environment variables are normally used for debugging or for changing license default location.

How to Set Environment Variables

FlexNet Publisher environment variables are set in two different ways:

- In the process' environment
- In the registry (Windows version 6.0 or earlier) or in `$HOME/.flexlmrc` (UNIX version 7.0 or earlier), which functions like the registry on UNIX.

Windows Registry

On Windows systems later than Windows XP, the location is **HKEY_LOCAL_MACHINE\SOFTWARE\FNPlm\License Manager** path for 32bit OS and creates the key in **HKEY_LOCAL_MACHINE\SOFTWARE\Wow6432Node\FNPlm\License Server** path for 64bit OS.

On UNIX, the equivalent information is stored in `$HOME/.flexlmrc`. In this file, the syntax is *variable=value*.

Precedence

If the variable is `LM_LICENSE_FILE` or `VENDOR_LICENSE_FILE`, then both the environment and the registry are used, with the environment used first, and the registry appended to the path.

If it's a different variable, then if the environment is set, only that is used, otherwise the registry is used. That is, the registry is only used if the environment is not set.

Environment Variables

The table below provides various environment variables and their definitions:

Table 24-1 • Environment Variables

Variable	Definition
EVENTTIMEOUT	<p>(Windows only) Sets the maximum amount of time (in microseconds) that the license-server service (lmadmin or lmgrd) waits for the vendor daemon to start before switching to a "Running" status:</p> <ul style="list-style-type: none">• If this variable is not defined, the default value 60000 is used.• If the vendor daemon starts before the time limit is reached, the server service switches to "Running" once the vendor daemon starts.• When the time limit is reached and the vendor daemon has not yet started, the server service does not start.• A zero (0) value means that the server service does not attempt to start at all. <p>This variable is especially useful in scenarios where the FlexEnabled client and license server are both running as services on the same machine. If the client service has a dependency on the license-server service, checkouts fail if vendor daemon is not running. Adjust this variable to allow enough time for the vendor daemon to start, thus increasing the likelihood of synchronization between service startups and initial checkouts.</p>
FLEXLM_BATCH	<p>(Windows only) Prevents interactive pop-ups from appearing. Set to 1 if a batch application. (Version 7.0 and later clients)</p>
FLEXLM_DIAGNOSTICS	<p>Used for debugging where applications do not print error message text. Set to 1, 2, or 3, depending on the amount of diagnostic information desired. See FLEXLM_DIAGNOSTICS (Version 5.0 and later clients)</p>
FLEXLM_TIMEOUT	<p>(Windows only) Sets the timeout value a FlexEnabled application uses when attempting to connect to a license server. Values are in microseconds, within the range of 200,000 (0.2 seconds) through 20,000,000 (20 seconds). The default value is 3,000,000 microseconds (that is 3 seconds).</p>
LM_BORROW	<p>Used for initiating license borrowing and setting the borrow period. See Initiating License Borrowing for more details. On UNIX platforms, \$HOME/.flexlmborrow is used for the registry instead of \$HOME/.flexlmrc.</p>
LM_LICENSE_FILE or VENDOR_LICENSE_FILE	<p>Reset path to license file. Can be a license search path, separated by ":" on UNIX and ";" on Windows. If VENDOR_LICENSE_FILE used, VENDOR is the vendor daemon name used by this application. For example, Flexera Software products use MVSN_LICENSE_FILE. Can be a file name, or <i>port@host</i>. See also Setting the License Search Path Using an Environment Variable (VENDOR_LICENSE_FILE requires version 6.0 and later clients).</p>

Table 24-1 • Environment Variables

Variable	Definition
LM_PROJECT	<p>LM_PROJECT's value (up to 30 characters) is logged in the report log file and later reported on by FlexNet Manager. It can also be used to RESERVE, INCLUDE, and so on licenses with PROJECT. For example:</p> <pre>RESERVE 1 f1 PROJECT airplane</pre> <p>The variable is read upon the license server's initial connection with the FlexEnabled client and is reread for each job, enabling you to update the variable value as needed on a job-to-job basis. However, the value with which a job initiates remains in effect for the duration of that job. You cannot modify this value mid-job.</p> <p> Note • This feature requires that the FlexEnabled client be built with FlexNet Publisher 5.0 or later and that the vendor daemon be built with FlexNet Publisher 7.0 or later.</p>
LM_SERVER_HIGHEST_FD	Used to set the highest file descriptor value, which controls the maximum number of client connections to the lmgrd is <= 1024. The default value for Windows is 4096 and for non-Windows is 1024. See Table 24-2, Comparison table with the behavior detail on Windows and Linux , on page 246
LM_UTIL_CASE_SENSITIVE	Used by the FlexLM utilities. If set to 1 , the utilities process license file lines as case sensitive. By default, this variable is set to 0 ; license files are treated as case insensitive. This environment variable is applicable only when the license server, itself, has been configured by your software publisher to treat license files in a case sensitive manner.
TCP_NODELAY	Improves license server performance when processing license requests. Set to 1 to enable performance enhancements. Use with caution: when enabled it may cause an increase in network traffic. Set TCP_NODELAY as System variables when setting the service to start at power up using lmtools.
FNP_IP_ENV	Improves the performance while checking out a license. When this environment variable value is set to 1 , the hostname resolution function calls are bypassed and the performance is improved.
FNP_IP_PRIORITY	Decides the IP priority for hostname resolution. By default IPv4 address resolution is used, if this resolution fails then it attempts for the IPv6 address resolution. Set FNP_IP_PRIORITY = '6' to use the IPv6 addresses resolution, if this resolution fails then it attempts for the default IPv4 address resolution.

Table 24-2 • Comparison table with the behavior detail on Windows and Linux

	WINDOWS		LINUX	
	lmgrd	VD	lmgrd	VD
Default maximum number of client connections	960 (as lmgrd will have some handles opened to access various Kernel system resources)	30,000	1023	Maximum number of client connections that can be handled by the OS.
Configuration option that adjusts maximum number of client connections	LM_SERVER_HIGHEST_FD	None	LM_SERVER_HIGHEST_FD	None
Absolute maximum number of client connections	960 (as lmgrd will have some handles opened to access various Kernel system resources)	30,000	1023	Maximum number of client connections that can be handled by the OS.
Debug Log message when maximum client connections are exceeded	Warning: Maximum connections to the server has reached. Please disconnect some clients from the server	None	Warning: Maximum connections to the server has reached. Please disconnect some clients from the server	None

Table 24-2 • Comparison table with the behavior detail on Windows and Linux

	WINDOWS		LINUX	
	lmgrd	VD	lmgrd	VD
Client error code received when maximum client connections are exceeded	If this_host is used in license file and if the server and client are on the same machine: -16 (LM_CANTREAD) If client is remote to server: -95 (LM_NOT_THIS_HOST)	None	If this_host is used in license file and if the server and client are on the same machine: -16 (LM_CANTREAD) If client is remote to server: -95 (LM_NOT_THIS_HOST)	None
Client error code received when lmgrd process is overwhelmed (as indicated by buildup of ESTABLISHED/ CLOSED_WAIT connections) with client connections before max client connections exceeded	-16 (LM_CANTREAD)	none	-16 (LM_CANTREAD)	none

Index

A

activatable license [18](#)
activation [17](#)
ANY hostid [53](#)
asset_info [36](#)
AUTH [33](#), [39](#)

B

BORROW_LOWWATER [155](#)
borrowing [61](#)

C

COMPOSITE
 hostid [53](#)
concurrent license [14](#), [18](#), [57](#)
 See also floating license
converting license formats [132](#)
creating a large user group [161](#)
creating options file [150](#)

D

debug log [14](#)
debugging license server [217](#)
DEBUGLOG [156](#)
decimal format licenses [132](#)
default license server ports [99](#)
DEMO hostid [53](#)
diagnosing checkout problems
 troubleshooting checkouts [127](#)
disabling

 Imdown [106](#), [118](#)
 Imremove [106](#), [118](#)
DISPLAY
 hostid [53](#)
 type [153](#)
dist_info [36](#)
DUP_GROUP [34](#)

E

enabling report log [169](#)
environment variables
 FLEXLM_BATCH [244](#)
 FLEXLM_DIAGNOSTICS [244](#)
 FLEXLM_TIMEOUT [244](#)
 LM_BORROW [244](#)
 LM_LICENSE_FILE [244](#)
 LM_PROJECT [245](#)
 LM_SERVER_HIGHEST_FD [245](#)
 setting [243](#)
 VENDOR_LICENSE_FILE [244](#)
error code
 descriptions [222](#)
 format [221](#)
EXCLUDE [156](#)
EXCLUDE_BORROW [157](#)
EXCLUDEALL [158](#)
expiration date [33](#)

F

feature
 version [32](#)
FEATURE line [31](#)
 asset_info [36](#)

- AUTH 33
- dist_info 36
- DUP_GROUP 34
- expiration date 33
- feature version 32
- FLOAT_OK 34
- HOST_BASED 34
- HOSTID 34
- ISSUED 34
- ISSUER 34
- license count 33
- ONE_TS_OK 35
- order of precedence 37
- OVERDRAFT 35
- serial number 35
- SIGN 33
- signature 33
- SN 35
- sort 36
- sorting order 37
- START 35
- SUITE_DUP_GROUP 35
- SUPERSEDE 35
- syntax 38
- TS_OK 36
- TZ 36
- USER_BASED 36
- user_info 37
- vendor daemon name 32
- vendor_info 37
- VENDOR_STRING 36
- VM_PLATFORMS 36
- FlexEnabled application 13
- FLEXLM License Finder 183
- FLEXLM_BATCH 244
- FLEXLM_DIAGNOSTICS 218
 - level 1 218
 - level 2 218
 - level 3 219
- FLEXLM_TIMEOUT 244
- FlexNet ID dongle with FLOAT_OK 60
- FlexNet Manager 169
- FLOAT_OK 34
- floating license 14, 57
 - See also concurrent license
- fulfillment record 13
 - example 22

G

- GROUP type 161
- GROUPCASEINSENSITIVE 161

H

- HOST type 153
- HOST_BASED 34
- HOST_GROUP type 162
- host, SERVER line 29
- HOSTID 34
- hostid 15
 - ANY 53
 - COMPOSITE 53
 - DEMO 53
 - DISPLAY 53
 - HOSTNAME 53
 - ID 54
 - INTERNET 54
 - SERVER line 29
 - special 53
 - USER 54
- HOSTNAME hostid 53

I

- ID hostid 54
- INCLUDE 162
- INCLUDE_BORROW 163
- INCLUDEALL 165
- INCREMENT line 31
- INTERNET
 - hostid 54
 - type 153
- IPv6
 - support overview 199
- ISSUED 34
- ISSUER 34

L

- license
 - borrowing 61
 - concurrent 57
 - contents 13
 - definition 13
 - floating 57
 - mixed 58
 - network license 57
 - node-locked 57
- license count 33
- license directory 108, 109
- license file 13
 - compatibility between different versions 215
 - FEATURE line 31
 - format 27
 - how to combine 213

- INCREMENT line 31
 - lminstall 132
 - order of lines 40, 58
 - PACKAGE line 38
 - rereading after an update 140
 - SERVER lines 215
 - specifying for license server 106, 118
 - specifying location 43
 - types 57
 - UPGRADE line 40
 - USE_SERVER line 31
 - VENDOR line 30
 - with multiple servers 107
 - License Finder 183
 - license model 13
 - license pool 32, 152
 - license rehosting 59
 - license search path 211
 - license server 13, 71, 105
 - alerts 71
 - debugging 217
 - default ports 99
 - disk space used 68
 - install as service 73, 88
 - install as Windows service 147
 - license rights 71
 - lmadmin 71
 - run in foreground 118
 - lmgrd 105
 - run in foreground 106
 - sockets used 67
 - specifying license files 106, 118
 - starting
 - lmadmin 73, 88
 - lmgrd 108
 - license server debug log
 - lmadmin 118
 - starting for lmgrd 106
 - license server manager 14, 71, 105
 - LINGER 166
 - LM_BORROW 244
 - LM_LICENSE_FILE 244
 - LM_PROJECT 245
 - reporting on project 169
 - use in options file 153
 - LM_SERVER_HIGHEST_FD 245
 - lmadmin 71
 - installing 72
 - license server manager not starting 81
 - starting 73, 88
 - manually 80
 - stopping 71, 81, 119
 - upgrading 77
 - lmdiag
 - syntax 127
 - troubleshooting 127
 - lmdown
 - disabling 106, 118
 - enabling for use with lmadmin 119
 - restricting access 93, 106, 118
 - syntax 127
 - lmgrd
 - and redundant servers 107
 - compatibility between versions 105
 - debug log file 237
 - starting 105, 108
 - starting debug log 106
 - syntax 105
 - use latest 241
 - lmhostid
 - syntax 128
 - lmhostid, syntax 128
 - lminstall
 - license file format 132
 - syntax 132
 - lmnewlog, syntax 133
 - lmremove
 - disabling 106, 118
 - enabling 120
 - restricting access 93, 106, 118
 - syntax 134
 - lmreread
 - restricting access 93, 106, 118
 - lmstat
 - output for lmreread 140
 - syntax 140
 - lmswitch, syntax 142
 - lmswitchr, syntax 144
 - lmtools 146
 - lmutil
 - lmdiag 127
 - lmdown 127
 - lmhostid 128
 - lminstall 132
 - lmnewlog 133
 - lmremove 134
 - lmstat 140
 - lmswitch 142
 - lmswitchr 144
 - lmver 145
 - lmver, syntax 145
- ## M
- MAX 166
 - MAX_BORROW_HOURS 168
 - MAX_OVERDRAFT 168
 - memory usage, daemons 68

- mixed licenses 58
- mobile licensing
 - borrowing 61
 - FlexNet ID dongle with FLOAT_OK 60
 - node-locked to FlexNet ID dongle 60
 - node-locked to laptop 59
 - node-locked to user name 65
 - prepaid license pool fulfillment 65

N

- network bandwidth and FlexNet Publisher 68
- network license 57
- node-locked license 57
- NOLOG 169

O

- ONE_TS_OK 35
- options file 14
 - BORROW_LOWWATER 155
 - creating 150
 - creating a large user group 161
 - DEBUGLOG 156
 - DISPLAY type 153
 - examples 172
 - EXCLUDE 156
 - EXCLUDE_BORROW 157
 - EXCLUDEALL 158
 - GROUP type 161
 - GROUPCASEINSENSITIVE 161
 - HOST type 153
 - HOST_GROUP type 162
 - INCLUDE 162
 - INCLUDE_BORROW 163
 - INCLUDEALL 165
 - INTERNET type 153
 - LINGER 166
 - MAX 166
 - MAX_BORROW_HOURS 168
 - MAX_OVERDRAFT 168
 - NOLOG 169
 - PROJECT type 153
 - read by vendor daemon 171
 - REPORTLOG 169
 - required for HOST_BASED 34
 - required for USER_BASED 36
 - RESERVE 170
 - rules of precedence 172
 - TIMEOUT 171
 - TIMEOUTALL 171
 - type argument 153
 - USER type 153
- options file path 31

- OPTIONS=SUITE 39
- OPTIONS=SUITE_RESERVED 39
- order of lines in license file 40, 58
- OVERDRAFT 35

P

- PACKAGE line 38
 - AUTH 39
 - OPTIONS=SUITE 39
 - OPTIONS=SUITE_RESERVED 39
 - SIGN 39
 - signature 39
 - syntax 38
- package suite 39
- port number
 - server default range 29
 - SERVER line 29
 - VENDOR line 31
- ports
 - license server 99
- precedence or FEATURE lines 37
- PROJECT type 153

R

- rehosting, license 59
- remote disks, guidelines for using 68
- report log 15
- report log file 68
- reporting on project 169
- REPORTLOG 169
- RESERVE 170
- restricting access
 - lmdown 93, 106, 118
 - lmremove 93, 106, 118
 - lmreread 93, 106, 118
- return 17

S

- SERVER line 28
 - combining license files 215
 - default port numbers 29
 - host 29
 - hostid 29
 - port number 29
 - syntax 28
 - three-server redundancy 28
- setting environment variables 243
- SIGN 33, 39
- signature 33, 39
- SN 35

- sockets
 - number used by license server [67](#)
- sort [36](#)
- specifying location of license file [43](#)
- START [35](#)
- starting lmadm [73, 88](#)
- starting lmgrd [108](#)
- status of license server [140](#)
- SUITE_DUP_GROUP [35](#)
- SUPERSEDE [35](#)
- switching debug log
 - lmswitch [142](#)
- switching report log
 - lmadm [119](#)
 - lmnewlog [133](#)
 - lmswitchr [144](#)

T

- three-server redundancy
 - separate license files [107](#)
 - SERVER lines [28](#)
- TIMEOUT [171](#)
- TIMEOUTALL [171](#)
- troubleshooting
 - with FLEXLM_DIAGNOSTICS [218](#)
 - with lmdiag [127](#)
- trusted storage [13, 17](#)
- TS_OK [36](#)
- TZ [36](#)

U

- UPGRADE line, syntax [40](#)
- USE_SERVER line [31](#)
- USER hostid [54](#)
- USER type [153](#)
- USER_BASED [36](#)
- user_info [37](#)

V

- vendor daemon [14](#)
 - and redundant servers [107](#)
 - debug log file [237](#)
 - lmnewlog [133](#)
 - lmreread [140](#)
 - lmswitchr [144](#)
 - memory usage [68](#)
 - options file [150](#)
 - report log [119](#)
 - VENDOR_LICENSE_FILE [244](#)
 - version compatibility [105](#)

- vendor daemon name
 - FEATURE line [32](#)
 - VENDOR line [30](#)
- vendor daemon path [31](#)
- VENDOR line [30](#)
 - options file path [31](#)
 - port number [31](#)
 - vendor daemon name [30](#)
 - vendor daemon path [31](#)
- vendor_info [37](#)
- VENDOR_LICENSE_FILE [45, 244](#)
- VENDOR_STRING [36](#)
- vendor.opt [31, 150](#)
- Vista [146, 243](#)
- VM_PLATFORMS [36](#)

