FLEXERA SOFTWARE

FLEXERA SOFTWARE™
FlexNet Publisher®

FlexNet Publisher 2016 (11.14.0)

Licensing for Java Programming Reference Guide

Legal Information

Book Name: Licensing for Java Programming Reference Guide

Part Number: FNP-11140-JPR00

Product Release Date: May 2016

Copyright Notice

Copyright © 2016 Flexera Software LLC. All Rights Reserved.

This product contains proprietary and confidential technology, information and creative works owned by Flexera Software LLC and its licensors, if any. Any use, copying, publication, distribution, display, modification, or transmission of such technology in whole or in part in any form or by any means without the prior express written permission of Flexera Software LLC is strictly prohibited. Except where expressly provided by Flexera Software LLC in writing, possession of this technology shall not be construed to confer any license or rights under any Flexera Software LLC intellectual property rights, whether by estoppel, implication, or otherwise.

All copies of the technology and related information, if allowed by Flexera Software LLC, must display this notice of copyright and ownership in full.

Intellectual Property

For a list of trademarks and patents that are owned by Flexera Software, see http://www.flexerasoftware.com/intellectual-property. All other brand and product names mentioned in Flexera Software products, product documentation, and marketing materials are the trademarks and registered trademarks of their respective owners.

Restricted Rights Legend

The Software is commercial computer software. If the user or licensee of the Software is an agency, department, or other entity of the United States Government, the use, duplication, reproduction, release, modification, disclosure, or transfer of the Software, or any related documentation of any kind, including technical data and manuals, is restricted by a license agreement or by the terms of this Agreement in accordance with Federal Acquisition Regulation 12.212 for civilian purposes and Defense Federal Acquisition Regulation Supplement 227.7202 for military purposes. The Software was developed fully at private expense. All other use is prohibited.

Contents

Introduction to this Document 7

Product Documentation 8

Identifying the Toolkit Directories 9

1 Getting Started with FlexNet Publisher Licensing Toolkit for Java. 11

Prerequisites 11

Evaluating the Licensing for Java. 11

Incorporating Licensing for Java into Your Product. 12

What's Installed 12

Licensing for Java and License Management 14

Licensing Toolkit Components 14

Unserved Licenses 14

Served Licenses 15

License Model Considerations 16

Supported Hostid Types. 16

Licensing Toolkit for Java and Security. 17

2 Evaluating the Licensing Toolkit for Java on UNIX. 19

Prerequisites 19

Add flexlm.jar to CLASSPATH 20

Create the demoInfo Class File. 20

Compile the Sample FlexEnabled Java Application 21

Create a Valid License File 22

Start a FlexNet License Server 23

Run the Sample Java Application 23

Stop the FlexNet License Server 23

3 Evaluating Licensing Toolkit for Java on Windows 25

Prerequisites 25
Add flexlm.jar to CLASSPATH 26
Create the demoInfo Class File 27
Compile the Sample FlexEnabled Java Application 28
Create a Valid License File 28
Start a License Server 29
Run the Sample Java Application 29
Stop the License Server 30

4 Incorporating Licensing Toolkit for Java Into Your Product 31
Configuring a Production Licensing Toolkit for Java 32
Define the CLASSPATH Environment Variable 32
Create the *vendor*Info.class File 33
Specifying the License File Location 33
Add Licensing Toolkit for Java API Function Calls to Your Product 34
A Basic Licensing Toolkit for Java Implementation 34
Testing Your Application 35
Create a License File 36
Start the License Server 36
Execute Your FlexEnabled Application 37
Deploying your Product 37

5 The Licensing Toolkit for Java API Programming Model 39
Licensing Toolkit for Java Framework 40
Feature Specifiers 40
License Sources 40
The VendorInfo class 41
Connection Data 42
Count 42
Checkout-Data Strings 42
Heartbeats 43
Automatic Heartbeats 44
Manual Heartbeats 45
Semi-Automatic Heartbeats 46
Hostids 47
Native Hostids 47
Vendor-Defined Hostids 49
FlexNet Publisher Licensing Toolkit for Java API 50
FlexNet Publisher Licensing Toolkit for Java Error Code Values 52

A Upgrading to FlexNet Publisher Licensing Toolkit for Java Version 11.x 57
Migrating to Version 11.x FlexNet Licensing for Java 57
Error Handling 58
Constants 58

Specifying the Feature to Check Out 59
Checkout and Checkin. 59
Heartbeats. 59
Accessing Data from the FEATURE/INCREMENT Line 60
Overriding User Name, Host, or Display 60
Migration Example. 61
Re-issuing Your Licenses. 64
Re-issuing Tamper-Resistant Licenses 65
Re-issuing Non Tamper-Resistant Licenses. 65
Supporting Multiple Deployed Versions 65
Distributing the Upgraded Application 65

Glossary 67

Index 79

Introduction to this Document

This manual, *Licensing for Java Programming Reference Guide*, provides:

- Instructions for evaluating FlexNet Publisher Licensing Toolkit for Java
- Instructions for incorporating FlexNet Publisher Licensing Toolkit for Java into your product
- Considerations for upgrading your existing FlexNet Publisher Licensing Toolkit for Java to version 11.10

Once you are familiar with FlexNet Publisher Licensing Toolkit and how it operates, work through either Evaluating the Licensing Toolkit for Java on UNIX or Evaluating Licensing Toolkit for Java on Windows in this manual with the provided example FlexEnabled Java program. Then, learn how to incorporate FlexNet Publisher Licensing Toolkit into your Java application in Incorporating Licensing Toolkit for Java Into Your Product. This section gives you an overview for incorporating calls to the FlexNet Publisher Licensing Toolkit Java API into your code, testing your application with a valid license, and deploying the final FlexEnabled Java application.

For FlexNet Publisher Licensing Toolkit issues not specific to Java, see either the *Programming Reference for License File-Based Licensing* or *Programming Reference for Trusted Storage-Based Licensing*.

Table -1 • *Licensing for Java Programming Reference Guide* Section Overview

Topic	Content
Introduction to this Document	Provides an overview of the *Licensing for Java Programming Reference Guide*.
Chapter 1, Getting Started with FlexNet Publisher Licensing Toolkit for Java	Gives a brief introduction to FlexNet Publisher Licensing Toolkit for Java, and requirements for use, and a brief overview of FlexNet Publisher Licensing Toolkit and its components.
Chapter 2, Evaluating the Licensing Toolkit for Java on UNIX	Walks you though the process of evaluating FlexNet Publisher Licensing Toolkit for Java behavior on UNIX.

Table -1 • *Licensing for Java Programming Reference Guide* Section Overview

Topic	Content
Chapter 3, Evaluating Licensing Toolkit for Java on Windows	Walks you though the process of evaluating FlexNet Publisher Licensing Toolkit for Java behavior on Windows.
Chapter 4, Incorporating Licensing Toolkit for Java Into Your Product	This chapter gives you the steps necessary to: • Configure FlexNet Publisher Licensing Toolkit for Java to work with your production FlexNet Publisher Licensing Toolkit. • Incorporate the calls to the FlexNet Publisher Licensing Toolkit for Java API into your own Java product. • Test your FlexEnabled Java product. • Deploy your application to your end user.
Chapter 5, The Licensing Toolkit for Java API Programming Model	Provides an in-depth overview of how to entitle a given feature of your FlexEnabled Java product, including how to successfully check out a license for that feature.
Appendix A, Upgrading to FlexNet Publisher Licensing Toolkit for Java Version 11.x	Provides information about upgrading from a pre 9.0 version of the Java toolkit.

Product Documentation

Flexera Software provides a comprehensive documentation set to assist you in working with the FlexNet Publisher. See the *Reference Bulletin for Documentation* for the current release for information about the most up-to-date documentation.

Identifying the Toolkit Directories

Table -2 lists the main toolkit directories and the shortcut names that are used to refer to them in the documentation.

Table -2 • Toolkit Directories

Shortcut Name	Default Location
`sdk_install_dir`	The directory where in install the toolkit. **Windows platforms:** No default, you define this path at installation time. **UNIX platforms:** No default, you define this path at installation time.

`sdk_platform_dir`	The directory within the toolkit that contains files specific to the operating-system platform of the toolkit. The folder label identifies this platform (such as x64_n6).
	Windows platforms:
	`<sdk_install_dir>\<sdk_platform_dir>`
	UNIX platforms:
	`<sdk_install_dir>/<sdk_platform_dir>`

`machind`	Toolkit files used to license your applications.
	Windows platforms:
	`<sdk_install_dir>\machind`
	UNIX platforms:
	`<sdk_install_dir>/machind`

`examples`	Sample code you can use as templates.
	Windows platforms:
	`<sdk_install_dir>\examples`
	UNIX platforms:
	`<sdk_install_dir>/examples`

1

Getting Started with FlexNet Publisher Licensing Toolkit for Java

This section covers necessary information to help you get started in using FlexNet Publisher Licensing Toolkit for Java, including prerequisites, component installation location and description, and security.

Prerequisites

Prior to incorporating FlexNet Publisher Licensing Toolkit for Java into your product, you must evaluate and then build your production toolkit.

Evaluating the Licensing for Java

Before evaluating FlexNet Publisher Licensing Toolkit for Java, you are required to complete the following:

- Install the FlexNet Publisher Licensing Toolkit toolkit. This is a separate package, from the FlexNet Publisher Licensing Toolkit for Java toolkit.
- Work through the sections in *Getting Started with License File-Based Licensing* corresponding to your development platform.
- Install the Sun Java Developers Kit on your development platform. See the FlexNet Publisher Licensing Toolkit Release Notes for information about the supported Sun JDK version.

Incorporating Licensing for Java into Your Product

In addition to the items in Evaluating the Licensing for Java, build your production toolkit customized with your private, vendor-specific information. (Tamper-Resistant Licenses (TRL) must be enabled.) See *Development Environment Guide* for details. Do this build before incorporating FlexNet Publisher Licensing Toolkit for Java into your application.

Note • *A C development environment is required to build the toolkit. Consult the documents, Development Environment Guide and the Release Notes for your platform's C development environment requirements.*

What's Installed

The subdirectories and components that comprise FlexNet Publisher Licensing Toolkit for Java are listed in Table 1-1. Paths are relative to the installation directory.

Table 1-1 • FlexNet Publisher Licensing Toolkit for Java Components

Component	Description
java/	
`EccpressoAll.jar`	FlexNet Publisher Licensing Toolkit for Java TRL classes. Needed at runtime if Tamper Resistant Licenses (TRL) are enabled.
`flexlm.jar`	FlexNet Publisher Licensing Toolkit for Java client classes. Needed at runtime.
`flexlmutil.jar`	FlexNet Publisher Licensing Toolkit classes used to generate your vendor-specific *vendor*`Info.java` file, where `vendor` is your vendor daemon name. Not needed at runtime.
`vendorInfo.bat (Windows)` `vendorInfo.sh (UNIX)`	Batch file to build *vendor*`Info.java` file if Tamper Resistant Licenses are not enabled. (Where `vendor` is your vendor daemon name.)
`flexlmmgmt.jar`	System file only. Do not use.
examples/	
`BasicExample.java`	Sample FlexEnabled Java application. Used during the FlexNet Publisher Licensing Toolkit for Java evaluation.

Table 1-1 • FlexNet Publisher Licensing Toolkit for Java Components

Component	Description
`ConnDataExample.java`	Example showing how to override the display name, hostname, username or servertimeout value when connecting to the license server.
`FeatureDetails.java`	Example showing how to get a feature list from a license source.
`HeartbeatExample.java` `HeartbeatWorker.java`	Set of examples showing how to configure heartbeats into your product.
`IndependentCheckouts.java`	The point of the example is to show multiple uses of a single feature on a single license server connection (LicenseSource instance), with separate checkins of various quantities, without the use of checkout data.
`MyHostId.java`	Example showing how to configure a vendor-defined hostid.
`TSExample.java`	Example showing how to use licenses held in trusted storage on a FlexEnabled client. It lists all the features available in local trusted storage and checks out and checks in one of those features.
`Documents/`	
`api/index.html`	The FlexNet Publisher Licensing Toolkit for Java API documentation.

Conflicting Usage of Certicom Security Library (EccpressoAll.jar)

FlexNet Publisher Licensing Toolkit for Java utilizes the security library `EccpressoAll.jar` from Certicom. In the event that your product also utilizes a different version of this library, there could be a clash during the Java library load. In such a case, use the `FlexnetPublisher.properties` file to mention the path of `EccpressoAll.jar`.

1. If the FlexNet Publisher Certicom jar file `EccpressoAll.jar` is in `D:\Certicom\lib`, for example, then create a `FlexnetPublisher.properties` file and, in that file, add the path as shown here:

   ```
   CerticomJarPath=d:/Certicom/lib/
   ```

2. Save the file and set the location of the file in the classpath. For example, if you save the file in `C:/flexjava` then set the classpath as shown here:

   ```
   set CLASSPATH=C:\flexjava
   ```

Note • *Use a forward slashes in the path of the jar file in properties file (all platforms).*

Licensing for Java and License Management

The FlexNet Publisher Licensing Toolkit for Java works in conjunction with the license server from the toolkit to provide a FlexEnabled Java application to your end user.

Licensing Toolkit Components

This section provides a basic overview of the components and their interaction with each other.

Components are organized based on your license model. License models are commonly classified according to their requirement for a license server:

- Licenses not served by a license server: they are available directly to the application. This is commonly referred to as an uncounted, or *unserved* license model.
- Licenses served by a license server: the licenses are available via a license server. The license server is either on the same system as the application or remote on the network. This is commonly referred to as a *served* license model. License files that include SERVER, VENDOR, and optionally, USE_SERVER lines require a license server. Optionally, uncounted, unserved licenses can be served in order to track usage.

Unserved Licenses

License models that do not need a license server have three components:

- The FlexEnabled Java product, which references the `com.macrovision.flexlm` classes in the FlexNet Publisher Licensing Toolkit for Java component, `flexlm.jar`.
- The `flexlm.jar` component, itself, from FlexNet Publisher Licensing Toolkit for Java.
- The license file, which is created with the `lmcrypt` utility from your production toolkit. Figure 1-1 shows this model.



Figure 1-1: Unserved License Component Model

The FlexEnabled application and license file reside on the same machine. All counted licenses in the local license file are ignored.

Even though a local license file may exist, there are some circumstances in which license requests are forwarded to a license server:

- The license file contains a USE_SERVER line, in which case all local FEATURE/INCREMENT lines are ignored. The request is forwarded to the server specified in the accompanying SERVER line.
- The FlexEnabled application cannot find the desired license in the local license file and a SERVER line is present. The request is forwarded to the specified server.

Served Licenses

For served licenses, there are five required components:

- The FlexEnabled Java application, which references the `com.macrovision.flexlm` classes in the `flexlm.jar` file.
- The `flexlm.jar` component, itself, from Licensing Toolkit for Java.
- The license server manager, `lmadmin` or `lmgrd`, from your production toolkit.
- The vendor daemon from your production toolkit. Along with the license server manager, `lmadmin` or `lmgrd`, this is a core component of the license server.
- The license file, which is created with the `lmcrypt` utility from your production toolkit.

In addition to these four components, there are three optional components:

- Debug log File—created and written by `lmadmin` or `lmgrd`.
- Report log File—created and written by the vendor daemon for use by FlexNet Manager.
- Options file—file created and maintained by the license administrator.

Figure 1-2 shows the relationship these components have to one another. Note that a distinction is made between FlexNet Publisher Licensing Toolkit toolkit components and FlexNet Publisher Licensing Toolkit for Java components. The final deliverable to your end user includes components from both areas.



Figure 1-2: Served License Component Model

Typically, the license server components reside on a system in the network. However, it can optionally reside on the same system as the FlexEnabled application.

The three optional files, Debug Log, Administration Options, and Usage Log, are configured by the license administrator at the customer site.

Note • *The environment variables,* `LM_LICENSE_FILE` *and* `VENDOR_LICENSE_FILE` *are not directly supported by FlexEnabled Java products.*

License Model Considerations

Supported Hostid Types

In order to control entitlement, the license file for an uncounted license model is node-locked to a specific hostid, which the FlexEnabled application then authenticates. However, because Java is so portable and generic, it is difficult to obtain a unique hostid directly from the Java product. The types of node-locked hostids that Licensing Toolkit for Java supports include the following:

- `DEMO`
- `ANY`
- `HOSTNAME=`*host_name*

- `INTERNET=xxx.xxx.xxx.xxx`
- `USER`
- `VM_UUID`

In addition, hostid lists are supported, so you can node-lock a license to a list of hostids. For example,

```
HOSTID="INTERNET=1.2.3.4 INTERNET=1.2.3.5 HOSTNAME=foo"
```

Wildcards are supported in address octets. If you choose to issue uncounted, node-locked licenses, we recommend that they expire.

In a served model, the license server authenticates the hostid; many more hostid choices exist in this configuration. For this reason, it is recommended that your end user uses a license server. The FlexEnabled Java application requests a license from the license server and is either granted or denied the license, with all authentication taking place at the license server level.

When using HOSTID in a feature line, you can use a wildcard character in the domain name. As an example, the following value allows the feature to be checked out by any hostname in the acress0 domain.

```
HOSTID=HOSTNAME=*.flexerasoftware.com
```

See Also
Hostids

Licensing Toolkit for Java and Security

There are special security considerations for companies using FlexNet Publisher Licensing Toolkit for Java because there aren't many possibilities for node-locked hostid types in the Java environment and Java applications can be relatively easily decompiled.

It is recommended that your end users use a license server rather than using node-locked uncounted licenses.

FlexNet Publisher Licensing Toolkit for Java supports Tamper Resistant Licenses (TRL), which are used to reduce the possibility of counterfeit licenses. TRL utilizes Certicom s public-key system based upon elliptical curve cryptography (ECC), which is considered secure, fast, and efficient (see http://www.certicom.com).

Companies upgrading from a version older than version 7.2i should refer to the *Programming Reference for License File-Based Licensing* for more information on Tamper Resistant Licenses.

2

Evaluating the Licensing Toolkit for Java on UNIX

This demonstration walks you though the process of evaluating Licensing Toolkit for Java behavior on UNIX. You perform the following to test the toolkit:

- Add the `flexlm.jar` to `CLASSPATH`
- Create the `demoInfo` Class file
- Compile the sample FlexEnabled Java application
- Create a valid license file
- Start the license server
- Run the application
- Stop the license server

Prerequisites

As a prerequisite for evaluating the Licensing Toolkit for Java:

- Install the Licensing Toolkit. This is a separately purchased package and is distinct from the Licensing Toolkit for Java.
- Work through the evaluation procedure for UNIX platforms in *Getting Started with License File-Based Licensing*.
- Install the Java Developers Kit on your development platform. See the *Release Notes* for information about the supported Sun JDK version.
- Install the Licensing Toolkit for Java.

The `machind` and `<sdk_platform>` (for example, `sun4_u5`) directories of the FlexNet Publisher Licensing Toolkit contain files that you use to evaluate the FlexNet Publisher Licensing Toolkit for Java. Locate the following files:

- `machind/lm_code.h`

- `<sdk_platform>/lmpubkey.h`

  Note • *If this file does not exist, you need to create it. To do so, from the* `<sdk_platform>` *directory, enter* `lmnewgen –pubkey`.

- `<sdk_platform>/lmseeds.h`
- Sample license file (`<sdk_platform>/lmadmin/demo/demo.lic`)
- License generation utility (`<sdk_platform>/lmcrypt`)
- License server manager--`lmadmin` (`<sdk_platform>/lmadmin/lmadmin`) or `lmgrd` (`sdk_platform/lmgrd`)
- Sample vendor daemon for `lmadmin` (`<sdk_platform>/lmadmin/demo/demo`) or for `lmgrd` (`<sdk_platform>/demo`)

  Note • *The license server* `lmadmin` *is used for this test. To use* `lmadmin`*, you must copy the vendor daemon* `demo` *and its associated library* `demo_libFNP.so` *from the* `<sdk_platform>` *directory to the* `<sdk_platform>/lmadmin/demo` *directory.*

Now you are ready to begin your evaluation of Licensing Toolkit for Java on UNIX.

Add flexlm.jar to CLASSPATH

To run a FlexEnabled Java application, you must set your `CLASSPATH` environment variable to include the current directory, the path to `flexlm.jar`, and the path to `EccpressoAll.jar`. If you installed the FlexNet Publisher Licensing Toolkit for Java toolkit into the default location, you would add to or set your `CLASSPATH` environment variable as follows:

```
setenv CLASSPATH .:<sdk_install_dir>/java/flexlm.jar: \
                 <sdk_install_dir>/java/EccpressoAll.jar
```

Make sure that the new `CLASSPATH` setting is active before proceeding.

Create the demoInfo Class File

Each software publisher must create a concrete subclass of `VendorInfo` containing vendor-specific information such as vendor name, encryption seeds, and vendor keys. An instance of a subclass of a `VendorInfo` must be associated with every `License` object. The name of the subclass is of the form `vendorInfo.class`, where `vendor` is the vendor name as registered with Flexera Software. The `demoInfo.class` is a subclass of `VendorInfo` for the vendor named `demo`.

Task: ***To create the subclass demoInfo.class***

1. Copy `machind/lm_code.h`, `<sdk_platform>/lmpubkey.h`, and `<sdk_platform>/lmseeds.h` from the `<sdk_install_dir>` directory to the `<sdk_install_dir>/java` directory.

   Note • *If* `lmpubkey.h` *does not exist, you need to create it. To do so, from the* `<sdk_platform>` *directory, enter* `lmnewgen -pubkey`.

2. Check that the following conditions are met:

   - `VENDOR_NAME` in `lm_code.h` is set to `"demo"`.
   - The `LM_STRENGTH` setting in `lm_code.h` is one of tamper-resistant licenses (TRL) settings and is the same as you used to build the production toolkit.
   - `lm_code.h` contains your demo vendor keys.

     This information is used to create a `demoInfo` class that is used to create a license object in your FlexEnabled application.

3. Change to the `<sdk_install_dir>/java` directory.

   In `vendorInfo.sh`, make sure the `-classname` switch specifies `demoInfo`. The contents of `vendorInfo.sh` should look like the example below:

```
java -classpath flexlmutil.jar;flexlm.jar; \
               EccpressoAll.jar \
      CreateVendorInfo -code lm_code.h -pubkey lmpubkey.h \
                       -seeds lmseeds.h \
                        -classname demoInfo
```

4. On the command line, execute `vendorInfo.sh` to create `demoInfo.java`.

5. Compile `demoInfo.java`:

```
javac -classpath flexlm.jar:EccpressoAll.jar demoInfo.java
```

6. Copy `demoInfo.class` into the `<sdk_install_dir>/examples` directory.

Compile the Sample FlexEnabled Java Application

Compile the sample FlexEnabled application, `BasicExample.java`, so it references `demoInfo.class`, which was created in Create the demoInfo Class File.

Task: ***To compile the sample FlexEnabled application***

1. Change to the `<sdk_install_dir>/examples` folder.
2. In `BasicExample.java`, check that the **`demoInfo`** constructor is properly referenced as in the excerpt below:

```
/*...*/
private static VendorInfo getVendorInfo()
{
    VendorInfo vInfo = null;
    try
    {
        vInfo = new demoInfo();
    }
/*...*/
    return vInfo;
}
```

3. Compile `BasicExample.java`:

```
javac -classpath \
      .:../java/flexlm.jar:../java/EccpressoAll.jar \
      BasicExample.java
```

Create a Valid License File

If not already generated during the Licensing toolkit evaluation, generate a counted license file, `counted.lic`, with `lmcrypt` from your Licensing toolkit. The contents of the license file must reflect the vendor and feature information that you put in the sample application.

Task: ***To create a valid license file***

1. Open `<sdk_platform>/lmadmin/demo/demo.lic` in a text editor.
2. Edit the `FEATURE` line, making sure it is similar to the following:

```
FEATURE f3 demo 3.0 permanent 4 SIGN=0
```

3. Save `demo.lic`.
4. Open a command window; and from the `<sdk_platform>` directory, enter the following:

```
lmcrypt ./lmadmin/demo/demo.lic
```

5. Verify that a signature was generated. The `FEATURE` line should now look something like this:

```
FEATURE f3 demo 3.0 permanent 4 SIGN="0008 0B78 63B1 1A00 DCE8 132C
   C70D 4A00 33E4 B817 F307 5041 8D0D 7A7A 2E47"
```

The number of hexidecimal characters in the license signature will correspond to the `LM_LICENSE` strength you selected in Step 1 of Create the demoInfo Class File.

Start a FlexNet License Server

In order to check out a counted **f3** license using the FlexEnabled application, you must start the license server. This process involves importing the vendor daemon `demo` and starting `lmadmin`. (When the license server starts, it uses the license file you just created in Create a Valid License File.)

Note • *In general, when starting the license server for the first time, use the command-line process, as described next. This test uses* `lmadmin` *as the license server.*

Task: ***To start the license server***

1. For purposes of this test, copy the vendor daemon `demo` and its associated library `demo_libFNP.so` from the `<sdk_platform>` directory to the `<sdk_platform>/lmadmin/demo` directory.
2. From the `<sdk_platform>/lmadmin` directory, enter the following to import the `demo` vendor daemon:

   ```
   lmadmin -import demo/demo.lic -force
   ```

3. Enter the following to start the license server in the background:

   ```
   lmadmin -adminOnly no -allowRemoteStopServer yes
   ```

Run the Sample Java Application

Task: ***To run the sample FlexEnabled Java application***

From the `<sdk_install_dir>/examples` directory, enter the following:

```
java -classpath \
        .:../java/flexlm.jar:../java/EccpressoAll.jar \
        BasicExample f3 3.0 @host
```

where `host` is the name of the machine on which the license server was started in Start a FlexNet License Server.

When you run the sample application, it will check out a license for version 3.0 of feature **f3**. Press **Enter** to check the license back in.

Stop the FlexNet License Server

Task: ***To stop the license server***

From the `<sdk_<platform>` directory, enter the following:

```
lmdown -c ./lmadmin/demo/demo.lic
```

You have completed the demo of the Licensing for Java toolkit on UNIX. When you are ready to incorporate your production vendor keys into the Licensing for Java toolkit, see Incorporating Licensing Toolkit for Java Into Your Product. Remember to set `LM_STRENGTH` to an appropriate value before you build your production Licensing toolkit. If you want to evaluate the Licensing for Java toolkit on Windows, see Evaluating Licensing Toolkit for Java on Windows.

3

Evaluating Licensing Toolkit for Java on Windows

This demonstration walks you though the process of evaluating FlexNet Publisher Licensing Toolkit for Java behavior on Windows.You perform the following to test the toolkit:

- Add the `flexlm.jar` to `CLASSPATH`
- Create the `demoInfo` Class file
- Compile the sample FlexEnabled Java application
- Create a valid license file
- Start the license server
- Run the application
- Stop the license server

Prerequisites

As a prerequisite for evaluating FlexNet Publisher Licensing Toolkit for Java on Windows:

- Install the FlexNet Publisher Licensing Toolkit toolkit. This is a separately purchased package and is distinct from FlexNet Publisher Licensing Toolkit for Java.
- Work through the FlexNet Publisher Licensing Toolkit evaluation for Windows platforms in *Getting Started with License File-Based Licensing*.
- Install the Java Developers Kit on your development platform. See the FlexNet Publisher Licensing Toolkit Release Notes for information about the supported Sun JDK version.
- Install the FlexNet Publisher Licensing Toolkit for Java.

The `machind` and `<sdk_platform>` (for example, `i86_n3`) folders in installation folder of the FlexNet Publisher Licensing Toolkit toolkit contain files that you use to evaluate FlexNet Publisher Licensing Toolkit for Java. Locate the following files:

- `machind\lm_code.h`
- `<sdk_platform>\lmpubkey.h`

  Note • *If this file does not exist, you need to create it. To do so, from the* `<sdk_platform>` *directory, enter* **`lmnewgen –pubkey`**.

- `<sdk_platform>\lmseeds.h`
- Sample license file (`<sdk_platform>\lmadmin\demo\demo.lic`)
- License generation utility (`<sdk_platform>\lmcrypt.exe`)
- License server manager, which is either `lmadmin` (`<sdk_platform>\lmadmin\lmadmin.exe`) or `lmgrd` (`<sdk_platform>\lmgrd.exe`)
- Sample vendor daemon for `lmadmin` (`<sdk_platform>\lmadmin\demo\demo.exe`) or `lmgrd` (`<sdk_platform>\demo.exe`)

  Note • *The license server* `lmadmin` *is used for this test. To use* `lmadmin`*, you must copy the vendor daemon* `demo.exe` *and its associated library* `demo_libFNP.dll` *from the* `<sdk_platform>` *directory to the* `<sdk_platform>\lmadmin\demo` *directory.*

Now you are ready to begin your evaluation of the FlexNet Publisher Licensing Toolkit for Java toolkit on Windows.

Add flexlm.jar to CLASSPATH

To run a FlexEnabled Java application, you must set your `CLASSPATH` environment variable to include the current directory, the path to `flexlm.jar`, and the path to `EccpressoAll.jar`. If you installed FlexNet Publisher Licensing Toolkit for Java into the default location, you would add to or set the following components in the `CLASSPATH` environment variable as follows:

```
C:\Program Files\Flexera Software\FLEXnet Licensing Toolkit for JAVA <version>\flexlm.jar; \
C:\Program Files\Flexera Software\FLEXnet Licensing Toolkit for JAVA <version>\EccpressoAll.jar
```

Make sure that the new `CLASSPATH` setting is active before proceeding.

Create the demoInfo Class File

Each software publisher must create a concrete subclass of `VendorInfo` containing vendor-specific information such as vendor name, encryption seeds, and vendor keys. An instance of a VendorInfo subclass must be associated with every `License` object. The name of the subclass is of the form *vendor*`Info.class`, where `vendor` is the vendor name as registered with Flexera Software.

Specifically, `demoInfo.class` is a subclass of `VendorInfo` for the vendor named `demo`. Follow the steps below to create the subclass `demoInfo.class`.

Task: ***To create the subclass demoInfo.class***

1. Copy `machind\lm_code.h`, `<sdk_platform>\lmpubkey.h`, and `<sdk_platform>\lmseeds.h` to the `<sdk_install_dir>\java` folder.

   Note • *If* `lmpubkey.h` *does not exist, you need to create it. To do so, from the* `<sdk_platform>` *directory, enter* `lmnewgen -pubkey`.

2. Check the following:

   - `VENDOR_NAME` in `lm_code.h` is set to `"demo"`.
   - The `LM_STRENGTH` setting in `lm_code.h` is one of Tamper Resistant Licenses (TRL) settings and is the same as you used to build the FlexNet Publisher Licensing Toolkit toolkit.
   - The file contains your demo vendor keys.

   This information is used to create a `demoInfo` class that is used to create a license object in your FlexEnabled application.

3. Change to the `<sdk_install_dir>\java` folder.

4. In `vendorInfo.bat`, make sure the `-classname` switch specifies `demoInfo`. The contents of `vendorInfo.bat` should look like the example given below.

```
java -classpath flexlmutil.jar;flexlm.jar; \
                EccpressoAll.jar \
      CreateVendorInfo -code lm_code.h -pubkey lmpubkey.h \
                       -seeds lmseeds.h \
                        -classname demoInfo
```

5. In an MS-DOS command window, execute `vendorInfo.bat` to create `demoInfo.java`.

6. Compile `demoInfo.java`:

   `javac demoInfo.java`

7. Copy `demoInfo.class` into the `<sdk_install_dir>\examples` folder.

Compile the Sample FlexEnabled Java Application

Compile the sample FlexEnabled application `BasicExample.java` so that it references `demoInfo.class` that was created in Create the demoInfo Class File.

Task: ***To compile the sample FlexEnabled application***

1. Change to the `<sdk_install_dir>\examples` folder.
2. In `BasicExample.java`, check that the **`demoInfo`** constructor is properly referenced as in the excerpt below:

```
/*...*/
private static VendorInfo getVendorInfo()
{
    VendorInfo vInfo = null;
    try
    {
        vInfo = new demoInfo();
    }
/*...*/
    return vInfo;
}
```

3. Compile `BasicExample.java`:

```
javac BasicExample.java
```

Create a Valid License File

If not already generated during the FlexNet Publisher Licensing Toolkit toolkit evaluation, generate the license file, `demo.lic`, using `lmcrypt` from your FlexNet Publisher Licensing Toolkit. The contents of the license file must reflect the vendor and feature information that you put in the sample application.

Task: ***To create a valid license file:***

1. Open `<sdk_platform>\lmadmin\demo\demo.lic` in a text editor.
2. Edit the `FEATURE` line, making sure it is similar to the following:

```
FEATURE f3 demo 3.0 permanent 4 SIGN=0
```

3. Save `demo.lic`.
4. Open an MS-DOS command window; and from the `<sdk_platform>` directory, enter the following:

   lmcrypt .\lmadmin\demo\demo.lic

5. Verify that a signature was generated. The `FEATURE` line should now look something like this:

```
FEATURE f3 demo 3.0 permanent 4 SIGN="0008 0B78 63B1 1A00 DCE8 132C
   C70D 4A00 33E4 B817 F307 5041 8D0D 7A7A 2E47"
```

The number of hexidecimal characters in the license signature will correspond to the `LM_LICENSE` strength you selected in Step 1 of Create the demoInfo Class File.

Start a License Server

In order to check out a counted **f3** license using the FlexEnabled application, you must start the license server. This process involves importing the vendor daemon `demo` and starting `lmadmin`. (When the license server starts, it uses the license file you just created in Create a Valid License File.)

Note • *In general, when starting the license server for the first time, use the command-line process, as described next. This test uses* `lmadmin` *as the license server.*

Task: ***To start the license server***

1. For purposes of this test, copy the vendor daemon `demo.exe` and its associated library `demo_libFNP.dll` from the `<sdk_platform>` directory to the `<sdk_platform>\lmadmin\demo` directory.
2. From the `<sdk_platform_dir>\lmadmin` directory, enter the following to import the `demo` vendor daemon:

   ```
   lmadmin -import demo\demo.lic -force
   ```

3. Enter the following to start the license server in the background:

   ```
   lmadmin -adminOnly no -allowRemoteStopServer yes
   ```

Run the Sample Java Application

Task: ***To run the sample FlexEnabled Java application***

From the `<sdk_install_dir>\examples` directory, enter the following:

```
java BasicExample f3 3.0 @host
```

where `host` is the name of the machine on which the license server was started in Chapter 3, "Start a License Server."

When you run the sample application, it will check out a license for version 3.0 of feature **f3**. Press **Enter** to check the license back in.

Stop the License Server

Task: ***To stop the license server***

From the <sdk_platform> directory, enter the following:

```
lmdown -c .\lmadmin\demo\demo.lic
```

You have completed the demo of FlexNet Publisher Licensing Toolkit for Java on Windows. When you are ready to incorporate your production vendor keys into FlexNet Publisher Licensing Toolkit for Java, see Incorporating Licensing Toolkit for Java Into Your Product. Remember to set `LM_STRENGTH` to an appropriate value before you build your production FlexNet Publisher Licensing Toolkit. If you want to evaluate FlexNet Publisher Licensing Toolkit for Java on UNIX, see Evaluating the Licensing Toolkit for Java on UNIX.

4

Incorporating Licensing Toolkit for Java Into Your Product

This section gives the steps necessary to:

- Configure Licensing Toolkit for Java to work with your production Licensing Toolkit. This involves setting the CLASSPATH environment variable and creating the `vendorInfo` vendor-specific class based on settings from your production Licensing Toolkit.
- Incorporate the calls to the Licensing Toolkit for Java API into your own Java product.
- Test your FlexEnabled Java product.
- Deploy your application to your end user.

Throughout this chapter, reference is made to several default directory locations for both the FlexNet Publisher Licensing Toolkit and the Licensing Toolkit for Java. Table 4-1 lists these locations and the shortcut terminology used in this chapter for each. Locate them in your installation and note their paths for reference when reading the rest of this chapter.

Table 4-1 • Licensing Toolkit for Java Contents

Shortcut	UNIX Default Location	Windows Default Location
FlexNet Publisher Licensing Toolkit Directories		
sdk_platform	`<sdk_install_dir>/<sdk_platform>`	`<sdk_install_dir>\<sdk_platform>`
sdk_machind	`<sdk_install_dir>/machind`	`<sdk_install_dir>\machind`
Licensing Toolkit for Java Directories		
flmjava_java	`<sdk_install_dir>/java`	`<sdk_install_dir>\java`
flmjava_examples	`<sdk_install_dir>/examples`	`<sdk_nstall_dir>\examples`

You are required to complete the following before proceeding with the instructions in this section:

- Build your production licensing toolkit customized with your private, vendor-specific information. See the document titled *Development Environment Guide* for details.

Note • *A C development environment is required to build the Licensing Toolkit for Java. See the document titled Development Environment Guide and the FlexNet Publisher Release Notes for your platform's C development environment requirements.*

All toolkit components must be generated from the same set of vendor keys (VENDOR_KEYs in lm_code.h) and encryption seeds (LM_SEEDs and any existing ENCRYPTION_SEEDs in lm_code.h).

- Install the Java Developers Kit.
- Install the Licensing Toolkit for Java.
- Work through the Licensing Toolkit for Java evaluation. See Evaluating the Licensing Toolkit for Java on UNIX and Evaluating Licensing Toolkit for Java on Windows.

Before proceeding, you need the following files and information from your production toolkit:

- `sdk_machind/lm_code.h`
- `<sdk_platform>/lmpubkey.h`
- `<sdk_platform>/lmseeds.h`
- the value of `VENDOR_NAME` from `sdk_machind/lm_code.h`
- The `LM_STRENGTH` setting from `sdk_machind/lm_code.h`

Configuring a Production Licensing Toolkit for Java

In order to configure the production licensing toolkit for Java, you must first define the `CLASSPATH` environment variable and then create the vendorInfo.class file.

Define the CLASSPATH Environment Variable

To run a FlexEnabled Java application, verify that the following components are included in your `CLASSPATH` environment variable:

- *flmjava_java*/`flexlm.jar`
- *flmjava_java*/`EccpressoAll.jar`

where `flmjava_java` is determined from Table 4-1.

Make sure that the new `CLASSPATH` setting is active before proceeding.

Create the *vendor*Info.class File

Each software publisher must create a concrete subclass of `VendorInfo` containing vendor-specific information such as vendor name, encryption seeds, and vendor keys. An instance of a VendorInfo subclass must be associated with every `License` object. The name of the subclass is of the form *vendor*`Info.class`, where `vendor` is the vendor name as registered with Flexera Software.

Note • *To create the subclass `vendorInfo.class`.:*

1. Copy `<sdk_machind/lm_code.h`, `<sdk_platform>/lmpubkey.h`, and `<sdk_platform>/lmseeds.h` from the `sdk_machind` directory to the `flmjava_java` directory.

   In `lm_code.h`, check that `VENDOR_NAME` is set to your vendor name, that the `LM_STRENGTH` has the desired value, and that the file contains your production vendor keys, encryption seeds, and TRL keys. This information is used to create a `vendorInfo` class that is used to create a license object in your FlexEnabled Java application.

2. In the `flmjava_java` directory, open `vendorInfo.bat` (Windows) or `vendorInfo.sh` (UNIX) in a text editor. Make sure the `-classname` switch specifies `vendorInfo`, where `vendor` is the name of your vendor daemon. The contents of `vendorInfo.bat` should look like:

```
java -classpath flexlmutil.jar;flexlm.jar; \
               EccpressoAll.jar \
      CreateVendorInfo -code lm_code.h -pubkey lmpubkey.h \
                       -seeds lmseeds.h \
                        -classname vendorInfo
```

3. In the `flmjava_java` directory, create the vendor-specific *vendor*`Info.java` file by executing `vendorInfo.bat` (Windows) or `vendorInfo.sh` (UNIX):

4. Compile *vendor*`Info.java` to create the class file `javac` *vendor*`Info.java`.

5. Copy *vendor*`Info.class` into the directory that contains your Java source file.

Specifying the License File Location

The most important part of integrating Licensing Toolkit for Java into your application is to correctly set the location of your the license file so it can be found at run time. This location should not be hard-coded, but should be determined at run time relative to your product's installation location.In the call to the **license** constructor, you must specify the path name of the license file. The following forms can be used to specify the license path:

- A single file, usually with the `.lic` extension. However, any extension can be used.
- *port@host*, where *port* is the port number and *host* is the host name of a license server. *port* can be omitted if it is within the default range of 27000–27009.

  Note • *For security purposes, best practice is not to use a default port for the license server. Instead, specify a port number outside of the range 27000 through 27009.*

- A three-server redundancy configuration, define it as *port@host1*, *port@host2*, *port@host3*

- A license file in a string. Precede the license certificate string with the string

  `FlexlmConstants.LICENSE_STRING_PREFIX`

  and end it with the string

  `FlexlmConstants.LICENSE_STRING_SUFFIX`

  Multiple license file locations can be concatenated together, separated by the "`&`" (ampersand) character.

Add Licensing Toolkit for Java API Function Calls to Your Product

This section describes how to modify your application code to call the FlexNet Publisher Licensing Toolkit for Java client API functions. This implementation is derived from `BasicExample.java` that is shipped with the Licensing Toolkit for Java and located in the `flmjava_examples` directory. This standalone example is a good place to start learning how to integrate the Licensing Toolkit for Java into your product.

Note • *A complete reference to the Licensing Toolkit for Java API Reference documentation is included in the distribution at the following location:*

Windows platforms:

```
<sdk_install_dir>\doc\api\index.html
```

UNIX platforms:

```
<sdk_install_dir>/doc/api/index.html
```

A Basic Licensing Toolkit for Java Implementation

In the simplest implementation, incorporating Licensing Toolkit for Java into your application involves these three classes:

- **vendorInfo**—Encapsulates the software vendor's encryption seeds, vendor keys, and other vendor-specific information.
- **FeatureSpecifier**—Specifies the details of the license to be checked out.
- **License**—Checks out and checks in the license.

Assuming a few exceptions that can be thrown by the Licensing Toolkit for Java methods are caught at an enclosing level, a basic implementation of Licensing Toolkit for Java involves the following steps:

1. Import the necessary classes from the `com.macrovision.flexlm` package into your code:

```
import vendorInfo;
import com.macrovision.flexlm.*;
```

`vendorInfo`, where `vendor` is your vendor name as registered with Flexera Software, is created externally. See Create the vendorInfo.class File for further information.

2. Instantiate a Feature Specifier for the desired feature.

   ```
   FeatureSpecifier featSpec = new FeatureSpecifier("f1", "1.0");
   ```

   In this example, the minimum specification is used to specify version `1.0` of feature `f1`. See Feature Specifiers for more details.

3. Specify the license search path used to locate license rights that entitle usage of the feature specified in Step 2.

   ```
   String licenseSourceString = "@localhost&c:\\MyDir\\licenses";
   ```

   This code specifies, in search order, the following two license sources:

   - `@localhost`—a license server running on the system `localhost`
   - `c:\MyDir\licenses`—a directory containing license files.

   Note the "&" used to separate these two components.

4. Instantiate a `License` object that fully qualifies the desired feature.

   ```
   License lic = new License(featSpec,
                             licenseSourceString,
                             new vendorInfo(), null);
   ```

   This `License` object is created from the feature specification, the license sources to use, and the vendor-specific information.

5. Now, check out a license and allow the FlexEnabled Java application code to execute.

   ```
   lic.checkout(1);
   ```

6. After the license is no longer needed, check it back in.

   ```
   lic.checkin();
   ```

   This checks in all instances of the feature that were checked out.

7. Make sure all Licensing Toolkit for Java methods are enclosed in a `try{}` block followed by a `catch(FlexlmException ex){/***/}` block. Alternatively, they can be in a method that throws `FlexlmException`.

8. Save and compile your source file.

9. Now you are ready to test your FlexEnabled Java application with the license server environment. Proceed to Testing Your Application.

Testing Your Application

Testing your application entails first creating a license file and then executing your application.

Create a License File

Your application needs a license file in order to test it. Generate a counted license file, mycounted.lic, using lmcrypt (available in the FlexNet Publisher Licensing Toolkit). The contents of the license file must reflect the vendor and feature information that you put in the sample application.

1. In the <platform_dir> directory make a copy of the file counted.lic and rename it to mycounted.lic.
2. Modify the SERVER, VENDOR, and FEATURE lines in mycounted.lic to include server information and information for the features that your application checks out. Place SIGN=0 at the end of each FEATURE line. See the *Programming Reference for License File-Based Licensing* for information about the allowed fields and syntax of a license file.
3. Save mycounted.lic.
4. In the <sdk_platform> directory of your Licensing Toolkit, sign mycounted.lic by typing **lmcrypt mycounted.lic**. This creates a valid license file by calculating signatures for each FEATURE line.
5. Move mycounted.lic to the directory containing your vendor daemon under the lmadmin installation directory.

Start the License Server

Task: ***To start the license server***

1. At a command prompt from the lmadmin installation directory, enter the following to start the license server:

   ```
   lmadmin -adminOnly no -allowRemoteStopServer yes
   ```

2. Close the command window.
3. To access the lmadmin user interface, open your Web browser, and enter the following URL:

   ```
   http://<server>:8090
   ```

   where

   - *<server>* is the system name where the license server is running.
   - 8090 is the port for the lmadmin user interface. If this is not the port you have assigned, change it to the correct one.

4. Select the Administration page, and sign in with your administrator credentials.
5. Go to the Vendor Daemon Configuration tab, and click **Import License**.
6. Click **Browse** to select the license file mycounted.lic.
7. Click **Import License** to import the vendor daemon.

Execute Your FlexEnabled Application

Task: ***To execute your application and check out a licence***

1. Make sure the following components are included in your CLASSPATH environment variable:

   flmjava_java/`flexlm.jar`
   flmjava_java/`EccpressoAll.jar`

2. Start your application, and perform a task that checks out one of its features.
3. Stop your application and the license server.

Deploying your Product

To ensure that your end users can use your FlexEnabled Java application easily and successfully, use the information in this section as a guideline for distributing your FlexEnabled Java application to the end user.

When you ship your FlexEnabled Java application, you need to include FlexNet Publisher Licensing Toolkit components in your software installation kit in addition to the files that you normally ship. Table 4-2 lists these additional components. Note that the components come from both the FlexNet Publisher Licensing Toolkit and the Licensing Toolkit for Java.

Table 4-2 • FlexNet Publisher Licensing Toolkit Components for Distribution

Component	Description
FlexNet Publisher Licensing Toolkit Components from the *sdk_platform* directory	
`lmadmin or lmgrd (lmadmin.exe or lmgrd.exe on Windows)`	The license server manager and vendor daemons. Include these if you distribute either counted or served-uncounted licenses.
vendor`.exe (Windows) or` *vendor* `(UNIX)`	
`lmutil.exe (Windows) or lmutil (UNIX)`	Used for license management and license server administration.
`lmtools.exe (Windows only)`	GUI front end to `lmutil.exe`.
`lmgr11.dll (Windows) or liblmgr11.so (UNIX)`	The client DLL or shared object used to support native hostid capabilities for FlexEnabled clients built with the Java toolkit.
FlexNet Publisher Licensing Toolkit for Java Components	
vendor`Info.class`	Subclass of the FlexNet Publisher Licensing Toolkit for Java VendorInfo superclass containing vendor-specific information.

Table 4-2 • FlexNet Publisher Licensing Toolkit Components for Distribution

Component	Description
`flexlm.jar`	Licensing Toolkit for Java classes.
`EccpressoAll.jar`	Licensing Toolkit TRL classes.

In addition to the components in Table 4-2, your customer eventually needs a license file. Depending on your internal policies, this can be shipped with your installation kit or shipped separately.

5

The Licensing Toolkit for Java API Programming Model

To entitle a given feature of your FlexEnabled Java application, the application needs to successfully check out a license for that feature. As such, the nucleus of the Licensing Toolkit for Java object model is represented by the `License` object. This object represents a specific usage of a feature. It encapsulates the following:

- The details of a feature (name, version, and so on) via a **FeatureSpecifier** object

  An application must specify the name of the feature to check out and the minimum acceptable version number of that feature. The application specifies this by creating a **FeatureSpecifier** object and passing that to one of the License constructors. See Feature Specifiers for more details.

- The count of the feature to check out

- The list of `LicenseSources` from which to try to check out

  Licenses can be checked out from license servers or from license files, which may refer to license servers. An array of `LicenseSource` objects is associated with each `License` instance by the constructor. One variant of the constructor accepts a `String` containing one or more license source specifiers, which are converted to an array of `LicenseSources` by the constructor. When checking out a license, the license source specified by each element of the array is tried, in order, to satisfy the checkout request. See License Sources for further details.

- The `LicenseSource` actually used for the checkout

  Over the course of its lifetime, a `License` may be checked out and back in many times, potentially from different `LicenseSource` objects. A `License` object can be associated with multiple `LicenseSource` objects over its lifetime, one at a time. The list of potential license sources with which it can be associated is established by the constructor. After a successful checkout, the actual `LicenseSource` instance that satisfied the checkout can be determined with the **getLicenseSource** method. Once a single `LicenseSource` is established in a `License` instance, it remains established as the sole `LicenseSource` for the life of the `License` instance.

- The checkout-data string associated with this `License`, if any

  A checkout-data string is used to label a feature checkout from a specific `License` object or to qualify a feature checkin request. The same checkout-data string can be associated with feature checkouts from multiple `License` objects. The checkout-data string can then be used to refer to all `License` objects using the same string, there by making it convenient to check in all licenses for the given feature with one invocation to the **checkin** method. See Checkout-Data Strings for more information.

Licensing Toolkit for Java Framework

This section covers the underlying framework for Licensing Toolkit for Java.

Feature Specifiers

In order to check out a license, the application must specify some details about the license to be checked out. At a minimum, an application must specify a feature name and the lowest acceptable version number of that feature. An application can specify additional details of the required license if it needs to. The application uses the `FeatureSpecifier` object to do this.

License Sources

A license is checked out from a license source, which can be any of the following:

- License file
- License server
- License in a string
- Local (client machine) trusted storage

In a basic implementation example, a list of license sources is specified from which to attempt a license checkout. This list is used to create an array of `LicenseSource` objects on behalf of the application.

An array of `LicenseSource` objects is associated with each License instance by the `License` constructor. One variant of the `License` constructor accepts a `String` containing one or more license source specifiers, which are converted to an array of `LicenseSource` objects by the constructor. When checking out a license, the license source specified by each element of the array is tried, in order, to satisfy the checkout request. The checkout may be satisfied by any one of the `LicenseSource` objects in the array, but only from one - not multiples.

After a successful checkout, the actual `LicenseSource` instance that satisfied the checkout can be determined with the **License.getLicenseSource** method. A `License` object can be associated with multiple `LicenseSource` objects over its lifetime, one at a time. The list of potential license sources with which it can be associated is established by the constructor.

Normally an application will leave the creation and management of `LicenseSource` objects to the `License` class. However, if the application wishes, it can manage `LicenseSource` objects itself. Variants of the `License` constructor take one, or an array of, existing `LicenseSource` objects as parameters. Alternatively, the **License.createLicenseSource** method can be used to create a single license source.

A `License` object created this way will try to check out a license from the supplied `LicenseSource` objects in the order specified. An application can create a `LicenseSource` object to be used in future `License` object instantiations by using the **LicenseSource.createLicenseSource** method. Also, an application can get the `LicenseSource` object associated with any given License object via the **License.getLicenseSource** method.

The following code demonstrates how to manage `LicenseSource` objects:

```
import vendorInfo;
import com.macrovision.flexlm.License;
import com.macrovision.flexlm.FeatureSpecifier;
import com.macrovision.flexlm.LicenseSource;
.
.
.
try
{
  // Set up specifications of features to check out
  FeatureSpecifier featSpec1 = new FeatureSpecifier("f1", "1.0");
  FeatureSpecifier featSpec2 = new FeatureSpecifier("f2", "1.0");

  // Set the license source string by hand.
  String licenseSourcesString =
      "7314@license.someserver.com&/opt/mypackage/licenses";

  // Create a VendorInfo instance for use with both
  // feature checkouts
  vendorInfo vInfo = new vendorInfo();

  // Create a license object for feature "f1" and check it out
  License lic1 = new License(featSpec1, licenseSourcesString, vInfo);
  lic1.checkout(1);

  // Get the license source used for the f1 checkout
  // and use it for checking out the f2 license.  Note that
  // we're invoking a License constructor that takes a
  // LicenseSource object this time (instead of a
  // String naming one or more LicenseSources).
  LicenseSource ls = lic1.getLicenseSource();
  License lic2 = new License(featSpec2, ls);
  lic2.checkout(1);
  .
  .
  .
  lic1.checkin();
  lic2.checkin();
{
catch (FlexlmException e)
{
  System.out.println(e.getMessage());
  System.exit(1);
}
```

The VendorInfo class

Each software publisher must create a concrete subclass of `VendorInfo` containing vendor-specific information such as vendor name, encryption seeds, and vendor keys. An instance of a subclass of a `VendorInfo` must be associated with every License object.

This class is created by a special utility program provided by Licensing Toolkit for Java that reads a data file containing the required information and writes a Java source file with the `VendorInfo` subclass. See Create the vendorInfo.class File for further information.

Connection Data

In some cases, an application may want to set connection-specific information that must be specified as part of the initialization of a connection to a license server, such as specifying a user name or heartbeat parameters. The application does this by creating an object that implements the ConnectionData interface and passing in that object when creating a LicenseSource or License object. The methods in the ConnectionData object are called on behalf of the application at the appropriate time during connection initialization.

IP Address Override

The FlexNet Publisher Licensing toolkit enables you to override the IP address of the client requesting the license for a specific feature. To support this IP-address-override functionality in a Java-based application, add the following API to your Java application code:

```
lic.setipaddress("<IP_address>");
```

where `<IP address>` is the value used in the `FEATURE` line or options file.

For more information, see the description for the `LM_A_INTERNET_OVERRIDE` attribute in the *C/C++ Function Reference*.

Note • *Add this API to the sample application,* `BasicExample.java`*, which ships with the Licensing toolkit for Java, if you want to test the IP-address-override functionality with the sample.*

Count

The **License.checkout** method checks out the specified count of the associated `Feature`. After the checkout method is called successfully, it may be called again any number of times with any count specified. The count is treated as the total complement of licenses required.

- If the count specified is the same as or lower than the count currently checked out, no additional licenses are checked out.
- If the count specified is higher than the number currently checked out, the `License` object attempts to check out just the additional count to meet the requested complement of licenses.

In this way, license server keeps a *high watermark* of the requested counts checked out.

Checkout-Data Strings

Up to 32 bytes of vendor-supplied data may be specified via **License.setCheckoutData** as a checkout-data string. As a label, this string is associated with checkouts and checkins of features from license servers. If no checkout-data string is specified, the `License` instance itself associates a unique checkout-data string with the checkout. This eliminates the need to write special code such as is necessary in non-Java applications to be able to check in a subset of the count checked out on a single license server connection.

Consider this example: an application wanting to check out a count of 10 of a given feature in two sets of five each, such that each set could be checked in independently on the same license server connection, can simply create two `License` instances that each check out a count of five. The `License` object's default management of checkout-data strings makes this possible.

Licensing Toolkit for Java does not allow checkouts in multiple `Feature` instances having any of the following:

- Same feature name in its `FeatureSpecifier`
- Same checkout-data string
- Same `LicenseSource`

Due to the way the license server behaves, allowing such checkouts could create ambiguities in the `License` instances. If a `License` instance attempts a checkout of the same feature, checkout data, and LicenseSource, it throws an exception.

A checkout-data string can also be used as a duplicate grouping criterion, in which case the application will want to manage checkout data strings itself.

See `LM_A_CHECKOUT_DATA` in the *C/C++ Function Reference* for more information about checkout-data strings.

Heartbeats

Heartbeats are messages exchanged between a FlexEnabled application and a license server for the purpose of assuring each that the other is still alive and healthy. By default, heartbeats are sent and received automatically by the FlexEnabled Java product. The only action necessary on the product's part is to provide methods to invoke when something in the heartbeat process goes wrong, for example, if the application can no longer communicate with the license server.

Heartbeats can be automatic, manual, or semi-automatic, the distinction being how the timing of heartbeat messages is managed and how reconnection attempts are recognized and handled. Table 5-1 summarizes these distinctions.

Table 5-1 • Heartbeat Summary

Type	Heartbeat Timing	Reconnection Management	Considerations
Automatic	FlexNet Publisher Licensing Toolkit creates and manages a dedicated thread to send and receive heartbeat messages at a specified interval on behalf of the application. The application controls the interval.	Reconnection to license server is handled automatically and transparently.	• Requires the application be multithreaded. • Simplest method to implement. No setup required by the application. • Dedicated heartbeat thread, rather than the application, is automatically interrupted.

Table 5-1 • Heartbeat Summary

Type	Heartbeat Timing	Reconnection Management	Considerations
Semi-automatic	Control of heartbeat timing regulated by the frequency with which the application invokes a particular method.	Reconnection to license server is handled automatically and transparently.	• No multithreaded requirement. • Requires application to setup heartbeat parameters. • Total control of interrupts to the application.
Manual	Control of heartbeat timing regulated by the frequency with which the application invokes a particular method.	Application detects reconnection attempts from the license server and determines how to respond.	• No multithreaded requirement. • Requires application to setup both heartbeat and reconnection parameters. • Total control of interrupts to the application.

An application may wish to temporarily suspend the sending of heartbeats so that the license server's timeout mechanism can reclaim a license that is not in active use. The `Heartbeat.setHeartbeatBlocked(boolean)` method provides a way for the application to specify the blocking and unblocking of heartbeats. Heartbeats are unblocked by default.

Automatic Heartbeats

By default automatic heartbeats are set up by FlexNet Publisher Licensing Toolkit for Java at license checkout time with the following default parameters:

- A heartbeat is sent to the license server every 120 seconds.
- Reconnecting to a lost license server tried every 60 seconds for up to five attempts.
- If connection is not re-established after five retries, **System.exit** is invoked to terminate the Java virtual machine.

If an application wishes to have different heartbeat and reconnect parameters, it can create a `LicenseSource` or `License` object using a customized **ConnectionData.initHeartbeat** method that calls the desired set methods in the `Heartbeat` object passed to it.

There are three possible outcomes with automatic heartbeats when reconnection is attempted after the connection to the license server is lost:

- Reconnection to the license server succeeded.
- Reconnection to the license server was attempted and failed, but more attempts will be made.
- Reconnection to the license server was unsuccessful after the retry limit was reached.

An application can supply code to execute at one or more of these junctures by providing an object implementing the `HeartbeatListener` interface and making it known via the **Heartbeat.addHeartbeatListener** method.

As an example, the code below implements **HeartbeatListener.reconnectFailed** method via a `HeartbeatAdapter` object to define the behavior in the event the reconnection retry limit is reached and reconnection is unsuccessful:

```
import com.macrovision.flexlm.Heartbeat;
import com.macrovision.flexlm.HeartbeatAdapter;
import com.macrovision.flexlm.HeartbeatEvent;
import com.macrovision.flexlm.LicenseSource;
import com.macrovision.flexlm.Feature;
.
.
.
ConnectionData connData = new ConnectionDataAdapter()
{
  public void initHeartbeat(Heartbeat hb)
  {
    hb.addHeartbeatListener(new HeartbeatAdapter()
    {
       public void reconnectFailed(HeartbeatEvent e)
       {
         // Get the name of the feature this event applies
         // to, and call the fictitious routine
         // "lostLicense()" to handle it from here.
         String featName = e.getHeartbeat().getFeature().
                           getName();
         lostLicense(featName);
      }
    });
  }
};
License lic = new License(featSpec,
                          licenseSourceString,
                          new vendorInfo(),
                          connData);
//See A Basic Licensing Toolkit for Java Implementation
//for definitions to featSpec, licenseSourceString,
//and vendorInfo.
```

Manual Heartbeats

Manual heartbeats are used instead of automatic heartbeats if the application:

- Wants to be in control of the precise timing of heartbeats.
- Cannot tolerate the extra thread introduced by automatic heartbeats.
- Cannot be multithreaded.

Some applications have critical sections of code that cannot be interrupted. Manual heartbeats provide a way for the application to control when the heartbeat thread executes thereby not perturbing the critical sections.

To set up manual heartbeats, the application needs to do the following.

Table 5-2 • Manual Heartbeat Procedures

Step	Action	Description
Step 1	Call **Heartbeat.setHearbeatInterval(int)** with a value of zero from its **ConnectionData.InitHeartbeat** method.	It can store the `Heartbeat` object passed to that method, or later it can test its `LicenseSource` object to see if it is an instance of `Heartbeat` and cast to it.
Step 2	Invokes **Heartbeat.sendHeartbeat** at whatever interval is deemed appropriate.	The **sendHeartbeat** method returns the number of unacknowledged heartbeats since the last successful one.
Step 3	Subsequently, as needed, invoke **Heartbeat.getReconnects(int)** to determine the number of reconnections over an application-supplied time interval.	This value and the return value from **sendHeartbeat** are helpful to the application in determining the health, over time, of the license server and the probability that license servers are being restarted maliciously.

Semi-Automatic Heartbeats

Semi-automatic heartbeats combine aspects of automatic heartbeats and manual heartbeats. With semi-automatic heartbeats, the application is in control of precise heartbeat timing (as with manual heartbeats), but the scheme of HeartbeatListeners to notify the application of HeartbeatEvents (used with automatic heartbeats) applies.

To set up semi-automatic heartbeats, the application needs to do the following.

Table 5-3 • Semi-Automatic Heartbeat Procedures

Step	Action
Step 1	Initialize the heartbeat interval to 0 as with manual heartbeats.
Step 2	Implement a `HeartbeatListener` interface, as with automatic heartbeats.
Step 3	Call **Heartbeat.doHeartbeat**.

The **Heartbeat.doHeartbeat** sends a heartbeat and checks for a response just like **Heartbeat.sendHeartbeat** does with manual heartbeats, but it also calls the `HeartbeatListener` methods as with automatic heartbeats. The **doHeartbeat** method returns the same value as **sendHeartbeat**, so you can use that value along with the **getReconnects** method in the same manner as for manual heartbeats.

Hostids

A hostid is a means used to uniquely identify a specific machine. There are two different contexts in which a hostid is used.

- **A license**—The license is bound to one or more hostids. They are used to define which systems are licensed to run your product. These licenses are said to be *node-locked* to a specific machine.
- **A license server**—A hostid used to define which system is authorized to run a license server that serves licenses to your FlexEnabled Java product.

In the context of a license server, any hostid type can be used as long as it is supported by FlexNet Publisher Licensing Toolkit. However, for node-locked licenses, the application is responsible for determining the hostid of the system on which it is running. Since FlexNet Publisher Licensing Toolkit for Java is a pure-Java package, only a few hostid types are supported—those not requiring a platform-dependent Java implementation on which the application is running. Available hostids include:

- `DEMO`
- `ANY`
- `HOSTNAME=host_name`
- `INTERNET=IPv4_address`
- `USER`
- `VM_UUID`

In addition to the above, FlexNet Publisher Licensing Toolkit for Java provides indirect support for the full complement of native hostid types via the **VendorInfo.useNativeHostIds** method. Additionally, a hook is provided for vendor-defined hostids.

Native Hostids

Native hostids are provided transparently via Java Native Interface (JNI) hostid integration, and can be enabled with a single method invocation. By shipping platform-dependent native code, it is simple to use the non-Java FlexNet Publisher Licensing Toolkit code to provide hostid capability to FlexEnabled Java products.

Note • *This feature requires a FlexNet Publisher Licensing Toolkit. To build a toolkit with dongle support use the following command make -f makefile DONGLE=1. For more details on building a kit, refer to FlexNet Publisher Development Environment Guide.*

The following sections outline how to implement native hostid support.

Microsoft Windows Platforms

Task: ***To implement native hostid support on Windows platforms:***

1. Build the FlexNet Publisher Licensing Toolkit. Refer to *Development Environment Guide* for details on building the kit.
2. Build `lmgr11.dll` in the FlexNet Publisher Licensing Toolkit. To do so, enter the following from the `<sdk_platform>` directory in your toolkit installation:

   `nmake -f makefile DLL=1` to build lmgr11.dll without dongle support

   or

   `nmake -f makefile DLL=1 DONGLE=1` to build lmgr11.dll with dongle support

   This client DLL contains the hostid-object code that you must ship with your product.
3. In the Java virtual machine's `$PATH` environment variable, include the path to the folder containing `lmgr11.dll`. This is how the Java Virtual Machine locates code invoked through JNI.
4. In the Java source code, invoke the **useNativeHostIds** method on any `VendorInfo` subclass instances that are created by the application code.

UNIX Platforms

Task: ***To implement native hostid support on UNIX platforms***

1. Build the FlexNet Publisher Licensing Toolkit. Refer to *Development Environment Guide* for details on building the kit.
2. Build `liblmgr11.so` in the FlexNet Publisher Licensing Toolkit. To do so, enter the following from the `<sdk_platform>` directory in your toolkit installation:

   `make shared_object`

   This shared object contains the C functions required to support Java native hostids.
3. Set the `LD_LIBRARY_PATH` system environment variable to include the path to `liblmgr11.so`.
4. In the Java source code, invoke the **useNativeHostIds** method on any `VendorInfo` subclass instances that are created by the application code. See the online API documentation for details on the **VendorInfo.useNativeHostids** method.

Vendor-Defined Hostids

A vendor-defined hostid hook is provided for applications that wish to use hostid types beyond those provided either directly by FlexNet Publisher Licensing Toolkit for Java or indirectly through the JNI interface. To use vendor-defined hostids, the application creates a subclass of the abstract `HostId` class. The subclass must implement several methods, including methods to do the following:

- Determine the value of the vendor-defined hostid of the current system
- Parse a hostid string and return a new object of this vendor-defined type
- Compare the hostid encapsulated in a `HostId` object to the hostid of the vendor-defined type of the current machine

A vendor-defined hostid type is registered at runtime via the **VendorInfo.registerVendorInfo** method.

Exceptions

The FlexNet Publisher Licensing Toolkit for Java API defines several exceptions. Each of the exceptions contains major and minor error numbers as in the FlexNet Publisher Licensing Toolkit toolkit, and the major error numbers are the same as those in the FlexNet Publisher Licensing Toolkit toolkit where possible. Table 5-5 lists the major error numbers that can be set by FlexNet Publisher Licensing Toolkit for Java API methods.

Various subclasses of the base exception class `FlexlmException` contain additional data describing the exception. The **FlexlmException.getMessage** method returns a localized error message according to the supplied `Locale` object and subject to the presence of a localized error message catalog file. An English version of this catalog is included in FlexNet Publisher Licensing Toolkit for Java as `FlexlmResources.properties`. This catalog is a sequence of `error_code=string values`. To localize the message catalog, create a separate properties file following the naming conventions outlined in the `java.util.ResourceBundle` class.

Task: ***To Implement vendor defined Hostids***

Ensure that you have started **FlexJava** Setup. This procedure is applicable for both Counted and Uncounted Licenses.

1. Open the `BasicExample.java` file and uncomment the following lines: (For Trusted storage based licensing edit TSExample.java file)

```
try {
vInfo.registerVendorHostId(new MyHostId("VDH=123"));
}
catch (FlexlmException e) {
System.out.println(e.getMessage());
System.exit(1);
}
```

Note • *If there exists a line "`vInfo.useNativeHostIds(true, null);`" in BasicExample.java file and TSExample.java file, then comment the line, as this will lock the HOSTID to lmhostid value and not VDH value.*

2. Open `MyHostid.java` file and change the return value of the last line to "123" and save the file.

3. Compile `BasicExample.java` file for license file based licensing or use `TSExample.java` file for trusted storage based licensing.
4. Now Crypt the license file.

```
SERVER this_host VDH=12345678 //Value present in vendor_hostid.c
VENDOR <vendor_name>
INCREMENT vd2 <vendor_name> 1.0 permanent 1 HOSTID=VDH=123 SIGN=0
```

5. Start the license server.
6. Checkout vd2 using *`javaclient(BasicExample or TSExample)`*.
7. Shut down the license server.

FlexNet Publisher Licensing Toolkit for Java API

The FlexNet Publisher Licensing Toolkit for Java API is defined by the `com.macrovision.flexlm` package. Figure 5-1 shows the major classes and interfaces comprising the `com.macrovision.flexlm` package (shaded background) and their relationship to each other and other Java components.



Figure 5-1: The `com.macrovision.flexlm` Package Hierarchy

Table 5-4 lists components contained in the `com.macrovision.flexlm` package. Definitions for each interface, class, and exception are located in the FlexNet Publisher Licensing Toolkit for Java distribution at the following location.

- Windows platforms: `<sdk_install_dir>\Documents\api\index.html`
- UNIX platforms: `<sdk_install_dir>/Documents/api/index.html`

Table 5-4 • The `com.macrovision.flexlm` Package

Name	Description
INTERFACES	
ConnectionData	Provides license server connection data.
FlexlmConstants	Constants used throughout the `com.macrovision.flexlm` package.
Heartbeat	Controls the heartbeats for a license source
HeartbeatListener	Provides callbacks for automatic heartbeats.
CLASSES	
ConnectionDataAdapter	Provides a default implementation of the `ConnectionData` interface.
Feature	Describes a FEATURE or INCREMENT line.
FeatureSpecifier	Specifies the details of the feature to be checked out.
FeatureUsage	Provides feature usage data items in response to **LicenseSource.getFeatureUsage**.
HeartbeatAdapter	Provides a default implementation for the `Heartbeat` interface.
HeartbeatEvent	Encapsulates the data passed to a `HeartbeatListener` object.
HostId	The superclass for providing vendor-defined hostids.
License	Represents the specific usage of a feature.
LicenseSource	The superclass of all classes from which `Feature` objects can be checked out.
ServerInfo	Information describing a license server's characteristics, primarily those expressed in the vendor daemon configuration file, `lsvendor.c`.
Userinfo	Encapsulates all the items known about a specific use of a feature checked out from a license server.
Userlist	Encapsulates data enumerating information known about each specific current use of a specified feature on a license server.

Table 5-4 • The `com.macrovision.flexlm` Package (cont.)

Name	Description
VendorInfo	The superclass for vendor-specific information.
EXCEPTIONS	
FlexlmException	Encapsulates the FlexNet Publisher Licensing Toolkit major and minor error numbers. See Table 5-5 for a list of major error numbers.
FlexlmLicenseElement Exception	Encapsulates exceptions that occur with a syntactically invalid license.
FlexlmListException	Encapsulates multiple `FlexlmException` objects into a list.

FlexNet Publisher Licensing Toolkit for Java Error Code Values

This section lists the error code values that are contained in the FlexlmException object; they are defined in `com.macrovision.flexlm.FlexlmResources.properties`. Values starting at -500 are specific to FlexNet Publisher Licensing Toolkit for Java. Values between -1 and -100 are defined in the FlexNet Publisher Licensing Toolkit C implementation and are included in this table for your convenience.

Table 5-5 • FlexNet Publisher Licensing Toolkit for Java Error Codes

Value	Symbolic Name	Description
-1	`LM_NOCONFFILE`	Can't Find License File
-3	`LM_NOSERVER`	No License Server System For This Operation
-4	`LM_MAXUSERS`	All Licenses In Use
-5	`LM_NOFEATURE`	No Such Feature Exists
-8	`LM_BADCODE`	Authentication Failed
-9	`LM_NOTTHISHOST`	Feature Is Locked To A Different Host
-10	`LM_LONGGONE`	Feature Is Expired
-12	`LM_BADCOMM`	Invalid Message Received From License Server System
-14	`LM_BADHOST`	Unknown Host
-15	`LM_CANTCONNECT`	Can't Connect to License Server System

Table 5-5 • FlexNet Publisher Licensing Toolkit for Java Error Codes

Value	Symbolic Name	Description
-16	LM_CANTRECEIVE	Can't Receive Data From License Server System
-17	LM_CANTSEND	Can't Send Data To License Server System
-18	LM_NOSERVSUPP	License Server System Does Not Serve This Feature
-20	LM_SERVBUSY	License Server System Busy (No Majority)
-22	LM_CHECKINBAD	Checkin Failed
-23	LM_BUSYNEWSERV	License Server System Temporarily Busy (New Server Connecting)
-24	LM_USERSQUEUED	Users Are Already Queued For This Feature
-25	LM_SERVLONGGONE	Server Does Not Support Feature Version Requested
-30	LM_NOREADLIC	Cannot Read License File
-31	LM_TOOEARLY	Start Date Not Yet Reached
-34	LM_CLOCKBAD	Clock difference too large between client and license server system
-35	LM_FEATQUEUE	Queue Entered
-38	LM_FEATEXCLUDE	User or Host is On The EXCLUDE List For This Feature
-39	LM_FEATNOTINCLUDE	User or Host is Not on the Options File INCLUDE List
-41	LM_BADPARAM	Invalid Parameter Passed To Method
-44	LM_BADKEYDATA	Invalid FlexNet Publisher Licensing Toolkit key data supplied
-48	LM_BADPLATFORM	FlexNet Publisher Licensing Toolkit platform not enabled
-50	LM_EXPIREDKEYS	FlexNet Publisher Licensing Toolkit key data has expired
-63	LM_NOTLICADMIN	License Administrator Privilege Required
-64	LM_REMOVETOOSOON	Attempt to Force Checkin Before Minimum Interval Elapsed
-77	LM_BAD_VERSION	Invalid Version Number Syntax
-82	LM_BADPKG	Invalid PACKAGE Line Syntax
-83	LM_SERVOLDVER	FlexNet Publisher Licensing Toolkit version of the Licensing client library newer than server

Table 5-5 • FlexNet Publisher Licensing Toolkit for Java Error Codes

Value	Symbolic Name	Description
-84	LM_USER_BASED	USER_BASED or HOST_BASED License, But No Users or Hosts Included in Options File
-88	LM_BADSYSDATE	System Date Has Been Set Back
-89	LM_PLATNOTLIC	This Platform Is Not Enabled By the License
-92	LM_SERVER_REMOVED	Server Removed During Re-Read, or Server HostId Mismatch With License
-101	LM_RESVFOROTHERS	All licenses are reserved for other users
-500	LM_BADPORT	Invalid Server Port Number
-501	LM_BADINTEGER	Invalid Value In License Where An Integer Was Expected
-502	LM_BADCOUNT	Invalid Value Supplied for Count
-503	LM_BADHOSTID	Invalid Hostid Supplied in License
-504	LM_BADHOSTIDTYPE	Invalid HostId Type Supplied
-505	LM_BADFEATURESYNTAX	Bad Feature Line Syntax
-506	LM_INTERNALERROR	Internal FlexNet Publisher Licensing Toolkit Error
-507	LM_BADDATE	Bad Date Format in License File
-508	LM_BADSERVERLINE	Bad SERVER Line
-509	LM_BADLICSTRING	Bad License String
-510	LM_FEATUREBADONSERVER	Server's Feature Doesn't Authenticate On Client Side
-511	LM_NOLICENSEOUT	No License Checked Out
-512	LM_LICENSEOUT	License Already Checked Out
-513	LM_ERRORLIST	Error List Returned
-514	LM_NOCERTICOM_MODULE	No Certicom Module Available
-515	LM_BADCERTICOM_MODULE	Wrong or Incomplete Certicom Module
-516	LM_SIGNREQUIRED	SIGN or SIGN2 Required in License Certificate
-517	LM_NOLICENSESOURCE	Feature Object Has No LicenseSources

Table 5-5 • FlexNet Publisher Licensing Toolkit for Java Error Codes

Value	Symbolic Name	Description
-518	LM_SAMELICENSE	An Identical License Is Already Checked Out On This License Source
-519	LM_CHECKOUTQUEUED	This License Has An Asynchronously Queued Checkout Pending
-521	LM_NONATIVELIB	Library for Native Hostid Couldn't Be Loaded
-522	LM_WRONGVENDOR	Already Connected to Another Vendor Daemon
-523	LM_NOUSER	No Such User, Host, or Display
-524	LM_SHUTDOWNFAILED	Shutdown of License Server System Failed
-525	LM_ALREADY_CONN	Shutdown Failed - Already Connected To License Server System
-526	LM_BADSOURCESPEC	Invalid License Source String
-527	LM_SWITCHERR	Log File Switch Error
-528	LM_CANTWRITEFILE	Cannot Write License File
-529	LM_BADOPTFILESYNTAX	Bad Options File Syntax
-530	LM_NATIVE_CALL_FAILED	Native Method Call Failed
-531	LM_NO_NATIVE_TS_LIB	Could not Load Native Library for TS Access
-532	LM_NOFEATURES	License Source Contains No Features

A

Upgrading to FlexNet Publisher Licensing Toolkit for Java Version 11.x

This appendix provides the necessary information you need to upgrade your existing FlexEnabled Java application from pre-version 9.0 to version 11.*x*.

If you are enabling FlexNet Publisher Licensing Toolkit for Java for the first time into your application, refer to Incorporating Licensing Toolkit for Java Into Your Product instead of this appendix.

Note • *Upgrading from a 10.0 or earlier version of FlexNet Publisher Licensing Toolkit for Java requires you to obtain version 10.0 or later of the FlexNet Publisher Licensing Toolkit toolkit (packaged separately), new vendor keys, and tamper resistant licenses (TRL) keys from Flexera Software before proceeding.*

Upgrading to FlexNet Publisher Licensing Toolkit for Java consists of:

- Configuring and building the FlexNet Publisher Licensing Toolkit with TRL enabled. See *Development Environment Guide* for details.
- Generating a `vendorInfo` subclass using the tools provided in the FlexNet Publisher Licensing Toolkit for Java distribution. See Create the vendorInfo.class File.
- Rebuilding your licensed application with the FlexNet Publisher Licensing Toolkit for Java classes. Note that the API has changed from the previous versions.
- Re-issuing licenses and deploying your upgraded application. See Re-issuing Your Licenses.

Migrating to Version 11.x FlexNet Licensing for Java

This section describes the individual areas for consideration when migrating your FlexEnabled Java application to the version 11.x API. To supplement the information in this section, consult the following reference:

- Incorporating Licensing Toolkit for Java Into Your Product

- The Licensing Toolkit for Java API Programming Model
- FlexNet Publisher Licensing Toolkit for Java API reference:
  - Windows platforms: `<sdk_install_dir>\Documents\api\index.html`
  - UNIX platforms: `<sdk_install_dir>/Documents/api/index.html`

Error Handling

Many methods in the version 11.x API throw a `FlexlmException`, or a subclass of `FlexlmException`, if a failure occurs. Thus, applications must invoke such methods from within `try` blocks followed by `catch` statements that catch `FlexlmException`. The contents of a `FlexlmException` include major and minor error codes, which are conceptually the same as in previous versions of FlexNet Publisher Licensing Toolkit for Java, in that it indicates the specific cause of the failure and a unique location in the source code where the error originated.

Table A-1 • Error Handling

Previous Behavior	Version 11.x Behavior
Method returns error codes to indicate success or failure.	Uses Java exceptions.

See Also
Exceptions
FlexNet Publisher Licensing Toolkit for Java Error Code Values

Constants

FlexEnabled Java products migrating to version 11.x can simply implement `FlexlmConstants` in their class definitions.

Table A-2 • Constants

Previous Behavior	Version 11.x Behavior
Defined in the `LM` class.	Defined in the `FlexlmConstants` interface.

Specifying the Feature to Check Out

The `FeatureSpecifier` instance object created is then passed as a parameter to other methods.

Table A-3 • Specifying Features

Previous Behavior	Version 11.x Behavior
Specified with parameters to license.checkout.	Specified with parameters to the **FeatureSpecifier** constructor.

Checkout and Checkin

The version 11.x `License` class is conceptually different than in previous versions. Previously, `license` was a collection of disparate entities related to checking a license out and in; the version 11.x `License` class has a more specific purpose: to encapsulate the details of a single feature usage. Hence, details like heartbeats, feature to check out, and the details of the feature actually checked out, are encapsulated in separate classes.

Note • *Queuing process is not supported on Java Client..*

Table A-4 • Checkout and Checkin

Previous Behavior	Version 11.x Behavior
Use license.checkout and license.checkin	Use **License.checkout** and **License.checkin**.

See Also
Count
Checkout-Data Strings

Heartbeats

In version 11.x, the default heartbeat style is automatic. An application controls heartbeat style and other heartbeat parameters by implementing the **ConnectionData.initHeartbeat** interface method and identifying the object implementing the interface to the `License` constructor. An application can do this either by implementing the `ConnectionData` interface directly (with the consequence of having to implement all the methods in the interface) or by subclassing the `ConnectionDataAdapter` class (only the methods for which non-default actions are required need

be implemented). In either case, to override heartbeat defaults, the **initHeartbeat** method must be overridden by the application. This method supplies a `Heartbeat` object, on which methods to control heartbeat actions are called by the application.

Table A-5 • Heartbeats

Previous Behavior	Version 11.x Behavior
Only manual heartbeats are supported	Automatic, semi-automatic, and manual heartbeats are supported

See Also
Heartbeats

Accessing Data from the FEATURE/INCREMENT Line

In version 11.x, the `Feature` class encapsulates `FEATURE/INCREMENT` line details. An application gets an instance of `Feature` after checkout via **License.getFeature**.

Table A-6 • Accessing Data

Previous Behavior	Version 11.x Behavior
Accessed via the `license` class.	Accessed via the `Feature` class.

Overriding User Name, Host, or Display

In version 11.x, the `ConnectionData` interface specifies methods to override user name, host, or display. An application can provide an instance of an object implementing these methods to the `License` constructor, or it can provide an instance of a subclass of `ConnectionDataAdapter`.

- The version 11.x defaults are:
  - **ConnectionDataAdapter.getUsername** returns the value of **System.getProperty("user.name")**.
  - **ConnectionDataAdapter.getHostname** returns the host name portion of **InetAddress.getLocalHost**.
  - **ConnectionDataAdapter.getDisplay** returns the constant `JavaDisplay`.
- In previous versions, the defaults are:
  - **license.getUsername** returns the constant `JavaUser`.
  - **license.getHostname** returns the host name portion of **InetAddress.getLocalHost**.

- **license.getDisplay** returns a zero-length `String`.

Table A-7 • Overriding User Name, Host, or Display

Previous Behavior	Version 11.x Behavior
Provided via `license` class methods.	Provided via the `ConnectionData` interface.

Migration Example

This section presents an annotated example with implementations in both the pre 9.0 version of FlexNet Publisher Licensing Toolkit for Java (on the left) and version 11.x (on the right). Reference numbers correspond to footnotes found after the example.

Table A-8 • FlexNet Publisher Licensing Toolkit for Java Migration Example

Version 9.0	Version 11.x

`import flexlm.*;`
`public class Example {`
	`import com.macrovision.flexlm.*;`[A]
	`public class Example`
	`implements FlexlmConstants` [B]
	`extends ConnectionDataAdapter{`
	`private static Heartbeat hb;`
	Note • *A: The package name* `com.macrovision.flexlm` *now conforms to Java package-naming conventions.*
	Note • *B: Constants useful to an application are defined in the* `FlexlmConstants` *interface.*

`public static void main(`
`String[] v){`
`license lic;`
`String path = "@localhost";`
	`public static void main(`
	`String[] v){`
	`String path = "@localhost";`
	`try` [C]
	`{`
	Note • *C: As most methods in the API throw* `FlexlmException`*, the method invocations are within a* `try/catch` *block.*

Table A-8 • FlexNet Publisher Licensing Toolkit for Java Migration Example

Version 9.0	Version 11.x

`String v = "demo";`
`int vk1 = 0x2fd9ed63;`
`int vk2 = 0x845567ba;`
`int vk3 = 0xcac3487f;`
`int vk4 = 0x724789df;`
`int vk5 = 0x49dcd926;`
	`DemoInfo dInfo = new DemoInfo();` [D]
	
	Note • *D: Vendor keys and encryption seeds are now encapsulated in a subclass of* `VendorInfo`*, generated and compiled externally. In this example, an instance of such a class is created with new* `DemoInfo`*.*

	`FeatureSpecifier fs = new FeatureSpecifier("f1","1.0");` [E] ***Note*** • *E: The feature name and feature version to check out are specified in a* `FeatureSpecifier` *object, which is then supplied to the* `License` *constructor.*

`license lic = new license(`
`v,`
`0x87654321^vk5,`
`0x12345678^vk5,`
`vk1, vk2,`
`vk3, vk4)`
`{`
`public String getUsername()`
`{`
`return System.getProperty(`
`"user.name");`
`}`
`public String getHostname()`
`{`
`return "myHost";`
`}`
`};`
	`License lic = new License(fs,`
	`path, dInfo, this);` [F]
	
	Note • *F: The* `License` *constructor takes*
	• *The* `FeatureSpecifier`*.*
	• *The path to the license file or license server.*
	• *The* `VendorInfo` *subclass instance.*
	• *An instance of a class implementing the* `ConnectionData` *interface. This interface includes methods to override hostname, username, and display, plus timeout interval and heartbeat initialization. This class extends the* `ConnectionDataAdapter` *class, which itself implements the* `ConnectionData` *interface, so the this object is passed as the last parameter.*
	• *An implementation of* **getUsername** *is provided, which overrides the default in* `ConnectionDataAdapter`*. Note that no implementation of* **getHostname** *is provided, as the default implementation in version 9.0 behaves exactly as the previous version does.*

Table A-8 • FlexNet Publisher Licensing Toolkit for Java Migration Example

Version 9.0	Version 11.x

`int rc = lic.checkout(`
`LM.RESTRICTIVE,`
`"f1",`
`"1.0",`
`1,`
`licpath);`
`if (rc != 0)`
`{`
`System.out.println(`
`"error: "+`
`Lic.get_errstring());`
`System.exit(1);`
`}`
	`lic.checkout(1);` G
	
	Note • *G: Checkout has a single parameter; the count of licenses to check out. The other entities specified in* **checkout** *method from previous versions are supplied in version 11.x in the* `License` *constructor instead. Note that there is no policy argument in version 11.x; all policy can be thought of as* `LM_RESTRICTIVE`.

`String vs = lic.getVendorString();`
`if (vs != null)`
`System.out.println(vs);`
	`Feature f = lic.getFeature();` H
	`String vs = f.getVendorString();`
	`if (vs != null)`
	`System.out.println(vs);`
	
	Note • *H: In order to get the vendor string in version 11.x, get a Feature object representing the* `FEATURE` *or* `INCREMENT` *line used to satisfy the checkout. This is done with* **License.getFeature**.

`int[] reconn = new int[1];`
`for (int i = 0; i < 60; i++)`
`{`
`int unAck = lic.heartbeat(`
`reconn, 60);`
`if (unAck > 5 || reconn[0] > 2)`
`{`
`System.out.println(`
`"too many reconns/unAck");`
`System.exit(1);`
`}`
`try { Thread.sleep(60*1000); }`
`catch (InterruptedException e){}`
`}`
	`for (int i = 0; i < 60; i++)`
	`{`
	`int unAck= hb.sendHeartbeat();  int reconn =`
	`hb.getReconnects(60);`
	`if (unAck > 5 || reconn > 2)`
	`{`
	`System.out.println(`
	`"too many reconns/unAck");`
	`System.exit(1);`
	`}`
	`try { Thread.sleep(60*1000); }`
	`catch(InterruptedException e)`
	`{}`
	`}`

`lic.checkin();`
`}`
`}`
	`lic.checkin();`
	`}`

Table A-8 • FlexNet Publisher Licensing Toolkit for Java Migration Example

Version 9.0	Version 11.x

	`catch(FlexlmException e)`
	`{`
	`System.out.println("error: "+`
	`e.getMessage());`
	`}`
	`}`
	`// overrides getHostname in`
	`// ConnectionDataAdapter`
	`public String getHostname()`
	`{`
	`return "myHost";`
	`}`
	`// overrides initHeartbeat in`
	`// ConnectionDataAdapter`
	`public void initHeartbeat(`
	`Heartbeat heartbeat)`
	`{`
	`hb = heartbeat;`
	`hb.setHeartbeatInterval(0);`
	`}`
	`}`
	
	Note • *In order to mimic the behavior of manual heartbeats in previous versions, override* **ConnectionData.initHeartbeat**. *In this implementation of* **initHeartbeat**, *save the* `Heartbeat` *instance so it can invoke its methods later, and set the heartbeat interval to 0, indicating manual heartbeats. To send a manual heartbeat,* `Heartbeat.sendHeartbeat` *is called. Like* `lic.heartbeat` *in previous versions, it returns the number of unacknowledged heartbeats since the last acknowledged heartbeat. Unlike previous versions, there is a separate method,* `Heartbeat.getReconnects`, *to get the number of reconnects over the specified number of minutes.*

Re-issuing Your Licenses

This section applies to those vendors upgrading from FlexNet Publisher Licensing Toolkit for Java versions prior to version 9.0.

Note • *Tamper Resistant Licenses (TRL) are referred to as the Counterfeit Resistant Option (CRO) in FlexNet Publisher Licensing Toolkit releases previous to version 10.0.*

Tamper resistant licenses (TRL) are the only authentication method supported by FlexNet Publisher Licensing Toolkit for Java version 11.x. In addition, TRL authentication in version 11.x is enhanced from previous versions of FlexNet Publisher Licensing Toolkit for Java. Therefore, you are required to re-issue existing licenses to your end user when you deploy your upgraded FlexEnabled Java product.

Re-issuing Tamper-Resistant Licenses

If you have issued TRL licenses prior to version 9.0, then you must re-issue them and distribute them along with your upgraded FlexEnabled Java application and, if required for your license policy, your upgraded vendor daemon. Use your existing license template that includes the `SIGN=` keyword. The new licenses must be generated with a version 11.x license generator built with FlexNet Publisher Licensing Toolkit components.

Re-issuing Non Tamper-Resistant Licenses

Since FlexNet Publisher Licensing Toolkit for Java version 11.x supports TRL authentication only, you must now issue TRL licenses with your upgraded product. Include the `SIGN=` attribute in your license template in place of the non-TRL signature field. The new licenses must be generated with a version 11.x license generator built with FlexNet Publisher Licensing Toolkit components.

Supporting Multiple Deployed Versions

To support multiple deployed versions of your product, a single license can be constructed that supports all current and past license authentication methods that use tamper resistant licenses. For instructions see 'Upgrading from Version 8.0 or Earlier' in *Development Environment Guide*.

Distributing the Upgraded Application

Follow the guidelines listed in Deploying your Product. Use your existing methods for re-issuing licenses; these may include using the `SUPERSEDE` keyword, `UPGRADE` line, or a rehosting procedure.

Glossary

Term	Meaning
activation specification record (ASR)	A signed XML file used with local activation and short code activation that contains information about license rights, configuration settings for the publisher's trusted storage segment, and additional information required by the activation transaction.
activatable license	A license right in trusted storage that can be activated to a FlexEnabled client. See also license group.
activation	In FlexNet Publisher Licensing Toolkit, this is a process used to load license rights into trusted storage. Different activation types include: • programmatic activation • manual activation • short code activation • local activation In FlexNet Operations, this is a process used to generate license rights in either trusted storage and in license files.
activated feature line	See feature definition line.
Activation API	Functions available in the FlexNet Publisher Licensing Toolkit libraries that allow you to initiate transactions and manage license rights in trusted storage. The Activation API is used to develop the functionality in an activation utility.

Term	Meaning
activation client	The system that works with an activation server to receive license rights. This system can be either a license server or a FlexEnabled client. The activation client initiates an activation, repair, or return transaction with an activation server, using an activation utility. The following transaction types can be initiated by an activation client: • activation transaction • return transaction • repair transaction
activation request	A message sent by an activation utility to an activation server that initiates an activation transaction.
activation response	A message sent from an activation server to an activation client, in response to an activation request. This message defines the license rights.
activation server	A system that responds to requests for license rights from an activation client. The activation server can be one of the following: • a license server • FlexNet Operations • an LGT-based activation server An activation server can also perform repair and return transactions.
activation transaction	A sequence of activation request and activation response messages, and related actions that result in license rights being loaded into trusted storage.
activation utility	A utility that initiates an activation transaction, repair transaction, or return transaction by sending a request to an activation server. This utility also processes the response received from the activation server. It uses the Activation API to perform these capabilities. It is written by the software publisher to meet specific business process requirements. This application can be either separate from or embedded in the FlexEnabled application.
anchor	A link between the system and the trusted storage that is used to detect whether trusted storage has been tampered with, deleted, or restored. Anchors are also used to ensure that information in trusted storage about trial licenses persists beyond the expiration date.
ASR file	See activation specification record (ASR).
binding	A capability used with trusted storage where one or more properties of a system, combined together into a unique identifier, are used to ensure that license rights held in trusted storage are not copied to another system.
borrowing	A capability available in FlexEnabled applications that enables a user to temporarily obtain a license in such a way that the license can be used locally for a limited period of time while the user is disconnected from the local network.

Term	Meaning
bulk entitlement	An entitlement created for an order of multiple copies of a single product or suite. Bulk entitlements are used for sales through reseller channels.
checkin	The transaction that a FlexEnabled application performs to return a license after it has been checked out. This operation is not the same as an activation transaction. FlexEnabled applications must perform a checkout and checkin transaction to use a license.
checkout	The transaction that a FlexEnabled application performs to request a license. This transaction is different than activating a license. FlexEnabled applications must perform a checkout and checkin transaction to use a license.
client system	A general term used to define any system that interacts with a server in a client-server relationship. When using FlexNet Publisher Licensing Toolkit there are two types of clients: • activation client • FlexEnabled client
concurrent license	A license that can be shared among users by allowing each user to check out and then return the license. These licenses are served to FlexEnabled applications from a license server. If all licenses are being used, an additional user cannot run the FlexEnabled application until one of the other users check in their license. When one user finishes using the license, another user can begin using it. Also called floating license or served license rights.
config response	A response to any request from an activation client that contains information about how the publisher's trusted storage segment must be configured (called the trusted storage segment configuration). This response is processed by the activation utility and results in a segment of trusted storage being created or re-configured for that publisher.
consumer	An individual or small business who purchases a license for their individual use. Compare with enterprise.
counted	A type of license right or license model that defines a multiple quantity of licenses and allows concurrent use of the licenses. This term is taken from the fact that the license server counts the number of licenses that are being used.
debug log file	A file used by the license server to record status and error messages that are useful for debugging the license server. Each license server can have one or more of these files.
demo license	See trial license.
duplicate grouping	A capability in the FlexNet Publisher Licensing Toolkit used to uniquely identify a single client (or client checkout request) for the purpose of counting the number of licenses that are used. Duplicate grouping defines a set of rules under which multiple checkout requests can share the same license(s).
embedded activation	See local activation.

Term	Meaning
encryption seed	A set of values defined by a software publisher that are used when creating a publisher-specific vendor daemon.
end-user	A person who uses a FlexEnabled application. This role is not the same as a license administrator.
end-user system	See client system.
end-user license administrator	See license administrator.
enterprise	An organization that purchases licenses on behalf of a number of individual users. Compare with consumer.
entitlement	A representation of the license model and product that a customer has bought. It is a definition only. The customer will need to fulfill the entitlement so that the license rights can be populated to license files or trusted storage. In FlexNet Operations, there are two types of entitlements: • bulk entitlement • simple entitlement Each entitlement is uniquely identified by an entitlement ID.
entitlement ID	In FlexNet Publisher Licensing Toolkit, an attribute in trusted storage that stores a value used to identify the customer's entitlement. In FlexNet Operations, a value that uniquely identifies the entitlement.
expiring license	License rights granted to a customer for a limited duration. When the license rights have expired, the licenses can no longer be checked out.

Term	Meaning
feature	In the context of a software application, this is a single unit of capability. In FlexNet Publisher Licensing Toolkit, this is an identifier used to associate a license model to a unit of capability in a software application. The software publisher defines which features in their software application map to a single feature in FlexNet Publisher Licensing Toolkit. For example, a feature in FlexNet Publisher Licensing Toolkit could represent any of the following: • The entire software application. • A subset of menu items. • A specific set of data available from the software application. • A process in the software application. The software publisher also defines the license model for each FlexNet Publisher Licensing Toolkit feature. This gives software publishers the ability to define a different license model for each feature in the software application.
feature bundle	A collection of features in FlexNet Operations. It exists primarily to enable modularity and re-use.
feature definition line	An entry in a license file or fulfillment record that describes a feature. Each line begins with the keyword FEATURE, INCREMENT, or UPGRADE. In license files, feature definition lines are used with SERVER and VENDOR lines to define the license model. In trusted storage, feature definition lines are used with the fulfillment record properties to define the license model.
feature line	See feature definition line.
file-based activation	See manual activation.
FlexEnabled application	A software application that uses FlexNet Publisher Licensing Toolkit to implement its license models.
FlexEnabled client	A client system where a FlexEnabled application is installed.
FLEXible API	Functions available in the FlexNet Publisher Licensing Toolkit libraries that allow FlexEnabled clients to access license rights.
FlexNet Agent	A utility that runs on a license server and allows communication between the license server and other FlexNet products.
FlexNet Manager	This is a license server management and license management decision support solution in the FlexNet product family that allows companies to centrally manage license servers and license usage across the enterprise.
FlexNet Operations	A product in the FlexNet family of products that manages entitlements and generates license rights.
floating license	A license that can be shared among users and is served to FlexEnabled applications from a license server. When a user finishes using the license, another user can begin using it. Also called concurrent license or served license rights.

Term	Meaning
fulfill	The action of getting license rights.
fulfillment record	In FlexNet Publisher Licensing Toolkit, a data structure specific to trusted storage that defines license rights.
heartbeat	A type of message sent periodically between two systems (for example, a FlexEnabled application and a license server) to identify whether each is running and able to communicate with the other.
hop count	In FlexNet Publisher Licensing Toolkit, the number of times that license rights in a single fulfillment record have been transferred from one license server to another.
hostid	In FlexNet Publisher Licensing Toolkit, the value of a specific system attribute that uniquely identifies the host. For example, if IP address is a hostid type, then the hostid might be 129.87.33.101. Hostids are used in node-locked license.
hostid type	A type of attribute that is available to uniquely identify a system. For example, disk serial number, IP address, or MAC address.
hybrid license	In FlexNet Publisher Licensing Toolkit, a type of license right in the license group on trusted storage that can function as either a concurrent license or as an activatable license.
internet activation	See programmatic activation.
keyboard activation	See short code activation.
license administrator	A person in an enterprise who is responsible for installing the FlexEnabled application and administering the licenses and license servers.
license file	A text file, usually with the .lic extension, that contains license certificates from one or more publishers.
license-file list	See license search path.
license generator	A general term used to describe any mechanism a software publisher uses to generate license rights for their customers. The following FlexNet capabilities and products can function as a license generator: • LGT-based activation server: generates license rights for trusted storage. • FlexNet Operations: generates license rights for trusted storage and license files. • lmcrypt: generates license rights for license files.
License Generator API (LGAPI)	A set of functions in the FlexNet Publisher License Generator Toolkit (LGT) used to create an activation server.
License Generation Toolkit (LGT)	A product in the FlexNet product line used to create an activation server.

Term	Meaning
license group	A mechanism used to describe licenses rights held in server-side trusted storage. These groups are not used with license rights held in license files. • **activatable**—A license right in trusted storage that can be activated to a FlexEnabled client. • **concurrent**—license rights in this group can be shared among users by having a FlexEnabled client to check out, and then return the license. • **hybrid**—these license rights have the same characteristics as both the activatable license group and concurrent license group. They can be activated to client-side trusted storage on a FlexEnabled client or checked out by a FlexEnabled client. Although you see these group names used to describe license rights in client-side trusted storage, the capabilities of the license rights do not change. Once license rights are in client-side trusted storage, you cannot transfer, serve, or activate them to another system. The FlexEnabled application can only check out and check in these licenses. The group names are used when a license right is returned to the license server, so that it is assigned to the correct license group on the license server.
license model	The set of characteristics that determine the conditions under which (for example, how, when, where, and by whom) a FlexEnabled application can be used.
license rights	Information in trusted storage or license files that defines the license model and controls user access to a specific FlexEnabled application.
license search path	A property that the FlexEnabled application uses to locate where license rights are stored. Sometimes known as a license-file list.
license server	A set of files from the FlexNet Publisher Licensing Toolkit, that work together to manage and serve licenses to FlexEnabled applications. A license server is required to support a concurrent license model. The license server consists of a license server manager, one or more vendor daemons, zero or more options files, zero or more debug logs, and, optionally, a report log. These components are available in the FlexNet Publisher Licensing Toolkit. If the license server supports license rights held in trusted storage, it also includes an activation utility. It may, optionally, act as an activation server.
license server system	See license server.
license server manager	A license server manager `lmadmin` or `lmgrd` executable that forwards connections from a FlexEnabled application to the correct vendor daemon. Because the vendor daemons are responsible for authenticating requests and serving licenses, a single license server manager can be used with multiple vendor daemons on the license server.
license sharing	A capability available in FlexNet Publisher Licensing toolkit where multiple license requests from the same user, host, or display results in only one license being used. Also known as duplicate grouping.
licensing client	See FlexEnabled client.

Term	Meaning
lmadmin	The license server manager introduced in version 11.6 which includes a Web-based GUI.
lmgrd	A command-line-based license server manager.
local license rights	License rights that are stored on the same system where the FlexEnabled application is running, rather than on a license server.
local activation	A type of activation where license rights are loaded using an ASR file. The ASR file must reside with the FlexEnabled application. This does not require user intervention.
machine ID	A value, generated using attributes of the system, that is used to bind trusted storage to that system.
maintenance	A maintenance represents a customer's right to obtain updates and upgrades to a particular licensed product or suite for a specified duration. Used in FlexNet Operations.
manual activation	An type of activation where license rights are transmitted from an activation server to another system using a set of request and response messages that are formatted as XML. These messages are saved to and read from physical XML files. An activation utility loads the license rights from an XML file into trusted storage.
node-locked license	A license that can be used only when the FlexEnabled application is run on a specific system or by a specific user (as defined by the hostid).
options file	A configuration file available on the license server that license administrators can use to either change license server behavior or implement certain licensing policies. Each software publisher has its own separate options file that works with a specific vendor daemon.
orderable	Anything that can be purchased by a customer. Orderables can include suites, products, documentation, and maintenances.
package	In FlexNet Publisher Licensing Toolkit, a set of features that can be grouped and licensed together.
part number	A unique identifier, typically correlated with an order system, assigned by a publisher to a product.
permanent license	License rights granted to a customer that do not expire.
product	Anything that can be sold by a publisher and can be licensed.
product ID	In FlexNet Publisher Licensing Toolkit, one of the values that uniquely identifies the license rights in trusted storage. See also entitlement ID.

Term	Meaning
programmatic activation	A type of activation where license rights are transmitted from one system to another across a network using a set of request and response messages that are formatted as XML. This process is the identical to manual activation, except that it does not generate a physical XML file. An activation utility loads the license rights from the XML message into trusted storage. This is an automated process and does not require user intervention.
publisher ID	A value used by trusted storage to uniquely identify the software publisher's logical and physical licensing components. Flexera Software distributes this identifier to software publishers. It is used to prepare certain FlexNet Publisher Licensing toolkit files that access trusted storage. This value is not the same as the vendor name.
quorum	A condition specific to three-server redundancy that is met when at least two of the three license servers are running and can communicate with each other using heartbeats.
rehost	The process of re-issuing a license for a different system. This process requires software publishers to perform certain activities to redefine the license rights so that they will work properly on the new system.
repair request	A message sent by an activation utility to an activation server that initiates a repair transaction. The activation server provides the information that repairs the license rights in trusted storage. An activation utility is an application that initiates the repair transaction.
repair response	A message sent from an activation server to an activation client, in response to a repair request. This message contains information that is used to the repair the license rights.
repair transaction	A sequence of repair request and repair response messages, and the related actions that result in license rights being repaired in trusted storage.
report log file	A file that runs on a license server that contains data about the features used by a single vendor daemon. Report logs are encrypted and cannot be read by a person, but are used by FlexNet Manager to produce reports.
return request	A message sent by an activation utility to an activation server that initiates a return transaction. The activation server receives the license rights returned by an activation client. An activation utility is an application that initiates the return transaction.
return response	A message sent from an activation server to an activation client, in response to a return request.
return transaction	A sequence of return request and return response messages, and the related actions, that result in license rights being returned from trusted storage to the activation server.
served license rights	License rights that are stored on a license server and are checked out when needed by FlexEnabled applications that run on client systems. These license rights are used for concurrent licensing.

Term	Meaning
short code	A multi-character code used with a short code activation transaction, a repair transaction, or a return transaction.
short code activation	A type of activation where license rights are loaded from an ASR file using an activation transaction that requires a specific code (called a short code). Often the user enters this code into a prompt from the application. This is also is used for licensing via automated telephony.
signature	A secure multi-character string added to the license certificate that ensures it has not been modified.
simple entitlement	An entitlement for a single, specific customer.
suite	A set products grouped together that are functionally complementary and associated with one or more license models.
supersede	A capability in FlexNet Publisher Licensing Toolkit, used to replace the characteristics of old license rights with new characteristics.
three-server redundancy	A capability in the FlexNet Publisher Licensing Toolkit that enables license administrators to configure three license servers in a failover cluster.
triad	A set of three license servers which operate together to support three-server redundancy.
trial license	License rights granted to a user for a limited duration so that the user can evaluate the software application.
trusted storage	A tamper-proof area on the system that stores license rights. This storage location is different than license files and requires a different mechanism for loading and managing license rights. Compare with license file.
trusted configuration	A set of attributes that define the security configuration of a segment of trusted storage. Each software publisher can configure their segments of trusted storage differently. This configuration defines the settings for binding, anchoring, and windback detection.
trusted configuration file	A file that stores the attributes that define a software publisher's trusted storage segment configuration.
trusted storage configuration	See trusted configuration.
uncounted	A license right attribute that allows an unlimited number of concurrent uses of a FlexEnabled application. Compare with counted.
unserved license rights	These are license rights that are not served from a license server. These license rights are located with the FlexEnabled application. Also known as local license rights.

Term	Meaning
upgrade	A process where a user installs a newer version of a FlexEnabled application and also updates the license rights so that they can use this newer version.
upsell	The process of transitioning from a product of lesser functionality to one of greater functionality in the same product line.
vendor daemon	One of the files that is a part of the license server. This executable is customized and built by the software publisher using files in the FlexNet Publisher Licensing toolkit. The vendor daemon is responsible for communicating with the FlexEnabled application and issuing licenses.
Vendor Certificate Generator	A publisher-built component, that is a part of FlexNet Operations, that creates license certificates or signed feature lines in fulfillment records. This functions similarly to lmcrypt.
vendor name	A value used to uniquely identify a software publisher's logical and physical licensing components. It is used to prepare certain files in the FlexNet Publisher Licensing toolkit that manage license rights in both trusted storage and license files. Flexera Software distributes this identifier to software publishers. This value is not the same as the publisher ID.
windback	A condition where the system clock has been set to an earlier date or time. One reason users change the system clock is to extend the license duration.
windback detection	A capability in FlexNet Publisher Licensing Toolkit that detects whether a user has reset the system clock. This prevents a user from extending the duration of the license.
windback tolerance	An acceptable amount of windback to a system clock that won't trigger windback detection. A certain tolerance is normally allowed to account for time zone differences or Daylight Saving Time.

Index

A

activatable license 67
activated feature line, See feature definition line
activation 67
    short code 76
activation API 67
activation application 68
activation client 68
activation request 68
activation response 68
activation server 68
activation specification record 67
activation transaction 68
anchor 68
application licenses 14
automatic heartbeats 44

B

basic implementation 34
binding 68
borrowing 68
bulk entitlement 69

C

checkin 69
checkout 69
checkout-data strings 42
class
    demoInfo 27
    vendorInfo 33
CLASSPATH 20, 26, 32
client system 69
concurrent license 69
config response 69
considerations, license model 16
consumer 69
counted license 69
counterfeit resistant option 64
CRO 64
customizing
    toolkit 12, 32

D

daemon, vendor 77
debug log file 69
demo license, See trial license
demoInfo Class, creating on UNIX 20
demoInfo class, creating on Windows 27
deployed files
    lmgr11.dll 38
    lmgrd 37
    lmtools.exe 37
    lmutil 37
    vendor daemon 37
deploying your application 37
duplicate grouping 69

E

embedded activation, See local activation
encryption seed 70
end user 70
end-user license administrator, See license administrator
end-user machine, See client system
enterprise 70
entitlement 70, 73

entitlement ID 70
error codes 52
error message localization 49
evaluation
    UNIX 19
    Windows 25
exceptions 49
executing your application 36
expiring license 70

F

feature 71
feature bundle 71
feature definition line 67, 71
feature specifiers 40
FEATURE/INCREMENT line, See feature definition line
file
    license 72
    options 74
    report log 75
file-based activation, See manual activation
files
    in package 12
FlexEnabled application 71
FlexEnabled client 71
Flexible API 71
flexlm.jar 20, 26
FlexNet Agent 71
FlexNet Publisher
    components 14
    UNIX evaluation 19
    Windows evaluation 25
FlexNet Publisher Operations 71
floating license 71
fulfill 72
fulfillment record 72

H

heartbeats 43, 72
    automatic 44
    manual 45
    semi-automatic 46
hop count 72
hostid 72
hostid type 72
hostid types 16
hostids, node-locked 16
hybrid license 72

I

implementation,basic 34
installation files 12
internet activation, See programmatic activation

J

Java API, adding to your application 34

K

keyboard activation, See short code activation

L

LGAPI 72
LGT 72
license
    counted 69
    served 75
    unserved 76
license administrator 72
license count 42
license file 72
license file, creating 22, 28, 36
license file, specifying the location 33
License Generation Toolkit 72
license generator 72
License Generator API 72
license group 73
license model 73
license model considerations 16
license rights 73
    local 74
license search path 73
license server 14, 73
license server manager 73
license server manager, definition 73
license server system 73
license server,starting 23, 29
license server,stopping 23, 30
license sharing 73
license sources 40
license-file list, See license search path
licenses
    served 15
    unserved 14
licenses, application 14
licensing client 73
lmadmin 74
lmgr11.dll 38
lmgrd 37, 74

lmtools 37
lmutil 37
local activation 74
local license rights 74
localization, error messages 49
locating the license server
    license file 33
    port@host 33
log file
    debug 69
    report 75

M

machineid 74
manual activation 74
manual heartbeats 45
model
    license 73

N

newlink GlossaryC 69
node-locked hostids 16

O

options file 74

P

package 74
part number 74
permanent license 74
port@host 33
prerequisites 11
product 74
programmatic activation 75
publisher id 75

Q

quorum 75

R

regular entitlement, See simple entitlement
rehost 75
re-issuing TRL licenses 64
repair request 75
repair response 75
report log file 75
return request 75
return response 75
return transaction 75

S

sample application, UNIX 21
sample application, windows 28
security 17
semi-automatic heartbeats 46
served license rights 75
served licenses 15
server
    license 73
short code 76
short code activation 76
signature 76
simple entitlement 76
starting a license server 23, 29
stopping a license server 23, 30
suite 76
supersede 76

T

tamper resistant licenses 17
testing your application 35
three-server redundancy 76
toolkit
    customizing 12, 32
triad 76
trial license 76
TRL licenses, re-issuing 64
trusted configuration file 76
trusted storage 13, 76
trusted storage configuration 76
type, hostid 72

U

uncounted license
    uncounted 76
UNIX evaluation 19
unserved license rights 76
unserved licenses 14, 76
upgrade 77
upsell 77

V

Vendor Certificate Generator 77
vendor daemon 37, 77
vendor name 77
vendor-defined host ids 47

vendorInfo.class, creating 33
VendorInfo() 41

W

what's installed 12
windback 77
windback detection 77
windback tolerance 77
Windows evaluation 25